

[illegible]

```

AAAAAA      CCCCCCCC  LL      SSSSSSSS  UU      UU  BBBB88888  RRRRRRRR
AAAAAA      CCCCCCCC  LL      SSSSSSSS  UU      UU  888888888  RRRRRRRR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AAAAAAAAAA  CC      SSSSSS  SS      UU      UU  BB8888888  RRRRRRRR
AAAAAAAAAA  CC      SSSSSS  SS      UU      UU  BB8888888  RRRRRRRR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CC      SS      SS      UU      UU  BB      BB  RR      RR
AA          AA  CCCCCCCC  LLLLLLLLLL  SSSSSSSS  UUUUUUUUUU  BBBB88888  RR      RR
AA          AA  CCCCCCCC  LLLLLLLLLL  SSSSSSSS  UUUUUUUUUU  BBBB88888  RR      RR

LL          IIIIII  SSSSSSSS
LL          IIIIII  SSSSSSSS
LL          II      SS
LL          II      SS
LL          II      SS
LL          II      SS
LL          II      SSSSSS
LL          II      SSSSSS
LL          II      SS
LL          II      SS
LL          II      SS
LL          II      SS
LLLLLLLLLLL  IIIIII  SSSSSSSS
LLLLLLLLLLL  IIIIII  SSSSSSSS

```

.....


```
0001 0 MODULE ACLSUBR (  
0002 0     LANGUAGE (BLISS32),  
0003 0     IDENT = 'V04-000',  
0004 0     ADDRESSING_MODE (EXTERNAL = GENERAL)  
0005 0 ) =  
0006 1 BEGIN  
0007 1  
0008 1 *****  
0009 1 *  
0010 1 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY  
0011 1 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.  
0012 1 * ALL RIGHTS RESERVED.  
0013 1 *  
0014 1 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED  
0015 1 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE  
0016 1 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER  
0017 1 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY  
0018 1 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY  
0019 1 * TRANSFERRED.  
0020 1 *  
0021 1 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE  
0022 1 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT  
0023 1 * CORPORATION.  
0024 1 *  
0025 1 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS  
0026 1 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.  
0027 1 *  
0028 1 *****  
0029 1  
0030 1 ++  
0031 1  
0032 1 FACILITY:      File system subroutines  
0033 1  
0034 1 ABSTRACT:  
0035 1  
0036 1     This module contains the subroutines that manage in memory  
0037 1     access control lists.  
0038 1  
0039 1 ENVIRONMENT:  
0040 1  
0041 1     Modular procedure. No own storage used.  
0042 1  
0043 1 --  
0044 1  
0045 1  
0046 1  
0047 1 AUTHOR:      L. Mark Pilant      CREATION DATE: 30-Sep-1982  11:00  
0048 1  
0049 1 MODIFIED BY:  
0050 1  
0051 1     V03-006 LMP0290      L. Mark Pilant,      31-Jul-1984  10:40  
0052 1     Make sure ACL_MODENTRY tracks the ACL_LOCATEACE interface  
0053 1     change.  
0054 1  
0055 1     V03-005 LMP0284      L. Mark Pilant,      25-Jul-1984  15:06  
0056 1     Add an ACL initialization routine, ACL_INIT_QUEUE.  
0057 1
```

```

58      0058 1 | V03-004 LMP0273      L. Mark Pilant,      6-Jul-1984 13:56
59      0059 1 |      Fix a bug that caused an ACE to be dropped when the user's
60      0060 1 |      buffer filled up during an ACL read.
61      0061 1 |
62      0062 1 | V03-003 ACG0426      Andrew C. Goldstein,    4-May-1984 15:14
63      0063 1 |      Fix clearing of input buffer in ACL_ERROR call in ACL_ADDENTRY
64      0064 1 |
65      0065 1 | V03-002 ACG0418      Andrew C. Goldstein,    19-Apr-1984 13:15
66      0066 1 |      Fix returning of NOMOREACE in reading ACL's
67      0067 1 |
68      0068 1 | V03-001 ACG0415      Andrew C. Goldstein,    3-Apr-1984 14:33
69      0069 1 |      Break out from SYSACLSRV.B32 to make common routines;
70      0070 1 |      rework add algorithm to: support multiple ACEs in one
71      0071 1 |      add, correctly protect positioning of alarm and audit
72      0072 1 |      ACEs at the front of the ACL, fix the block split of
73      0073 1 |      large ACLs; general code cleanup and minor bug fixes.
74      0074 1 |
75      0075 1 | **
76      0076 1 |
77      0077 1 | LIBRARY 'SYSS$LIBRARY:LIB.L32';
78      0078 1 | REQUIRE 'SRC$:FCPDEF';
79      1069 1 |
80      1070 1 |
81      1071 1 | FORWARD ROUTINE
82      1072 1 |     ACL_INIT_QUEUE,      | Initialize ACL queue
83      1073 1 |     ACL_ADDENTRY,        | add an ACE to an ACL
84      1074 1 |     ACL_DELENTY,        | remove an ACE from an ACL
85      1075 1 |     ACL_MODENTRY,       | modify an existing ACE
86      1076 1 |     ACL_FINDENTRY,      | locate a specific ACE
87      1077 1 |     ACL_FINDTYPE,       | locate a specific type of ACE
88      1078 1 |     ACL_DELETEACL,      | remove entire ACL from object
89      1079 1 |     ACL_READACL,        | read one or more ACEs
90      1080 1 |     ACL_ACLLENGTH,     | determine the size of the ACL
91      1081 1 |     ACL_READACE,        | read a single ACE
92      1082 1 |     ACL_LOCATEACE;      | locate ACE by context value
93      1083 1 |
94      1084 1 | EXTERNAL ROUTINE
95      1085 1 |     ALLOC_PAGED,        | Paged pool allocator
96      1086 1 |     DALLOC_PAGED;       | Paged pool deallocator
97      1087 1 |
98      1088 1 | MACRO
99      1089 1 |     ACL_ERROR (STATUS) =
100     1090 1 |         BEGIN
101     1091 1 |             CH$FILL (0, .COUNT, .ACE);
102     1092 1 |             ACE[ACES$W_FLAGS] = STATUS;
103     1093 1 |             RETURN STATUS;
104     1094 1 |         END
105     1095 1 |         %;
106     1096 1 |
107     1097 1 | ! Fields used in the ACL context longword.
108     1098 1 |
109     1099 1 | MACRO
110     1100 1 |     CONTEXT_INDEX      = 0, 0, 24, 0 %; ! ACL entry index
111     1101 1 |     CONTEXT_TYPE       = 0, 24, 8, 0 %; ! entry type in use
```



```
113 1102 1 %SBTTL 'ACL_INIT_QUEUE - initialize ACL queue head'
114 1103 1 GLOBAL ROUTINE ACC_INIT_QUEUE (ORB_ADDRESS) =
115 1104 1
116 1105 1 ++
117 1106 1
118 1107 1 FUNCTIONAL DESCRIPTION:
119 1108 1
120 1109 1 This routine is called to initialize an uninitialized ACL queue.
121 1110 1 If the queue has already been initialized, this routine is a no-op.
122 1111 1
123 1112 1 CALLING SEQUENCE:
124 1113 1 ACL_INIT_QUEUE (ARG1)
125 1114 1
126 1115 1 INPUT PARAMETERS:
127 1116 1 ARG1: address of the ORB
128 1117 1
129 1118 1 IMPLICIT INPUTS:
130 1119 1 none
131 1120 1
132 1121 1 OUTPUT PARAMETERS:
133 1122 1 none
134 1123 1
135 1124 1 IMPLICIT OUTPUTS:
136 1125 1 none
137 1126 1
138 1127 1 ROUTINE VALUE:
139 1128 1 1
140 1129 1
141 1130 1 SIDE EFFECTS:
142 1131 1 ACL queue head is initialized, and the ACL queue bit in the ORB
143 1132 1 is set.
144 1133 1
145 1134 1 --
146 1135 1
147 1136 2 BEGIN
148 1137 2
149 1138 2 MAP
150 1139 2 ORB_ADDRESS : REF BBLOCK; ! Address of the ORB
151 1140 2
152 1141 2 LOCAL
153 1142 2 ORB : REF BBLOCK; ! Address of the ORB for PRIMARY_FCB
154 1143 2
155 1144 2 EXTERNAL
156 1145 2 CTL$GL_PCB : REF BBLOCK ADDRESSING_MODE (ABSOLUTE);
157 1146 2
158 1147 2 LINKAGE
159 1148 2 L_MUTEX = JSB (REGISTER = 0, REGISTER = 4)
160 1149 2 : NOTUSED (5, 6, 7, 8, 9, 10, 11);
161 1150 2
162 1151 2 EXTERNAL ROUTINE
163 1152 2 SCH$LOCKW : L_MUTEX ADDRESSING_MODE (ABSOLUTE),
164 1153 2 ! Lock mutex for write
165 1154 2 SCH$UNLOCK : L_MUTEX ADDRESSING_MODE (ABSOLUTE);
166 1155 2 ! Unlock mutex
167 1156 2
168 1157 2 ! If the ACL queue head is uninitialized, do the initialization now.
169 1158 2
```

```

: 170      1159 2 ORB = .ORB ADDRESS;
: 171      1160 2 IF NOT .ORB[ORB$V_ACL_QUEUE]
: 172      1161 2 THEN
: 173      1162 2 BEGIN
: 174      1163 2     ORB[ORB$ACL_MUTEX] = %X'0000FFFF';      ! Initialize the ACL mutex
: 175      1164 2     SCH$LOCKW (ORB[ORB$ACL_MUTEX], .CTL$GL_PCB);
: 176      1165 2     ORB[ORB$V_ACL_QUEUE] = 1;
: 177      1166 2     ORB[ORB$ACL_FFL] = ORB[ORB$ACL_BFL] = ORB[ORB$ACL_FFL];
: 178      1167 2     SCH$UNLOCK (ORB[ORB$ACL_MUTEX], .CTL$GL_PCB);
: 179      1168 2     SET_IPL (0);
: 180      1169 2     END;
: 181      1170 2
: 182      1171 2 RETURN 1;
: 183      1172 2
: 184      1173 1 END;

```

! End of routine ACL_INIT_QUEUE

```

.TITLE  ACLSUBR
.IDENT  \V04-000\

.EXTRN  ALLOC PAGED, DALLOC PAGED
.EXTRN  CTL$GL_PCB, SCH$LOCKW
.EXTRN  SCH$UNLOCK

.PSECT  $CODE$,NOWRT,2

.ENTRY  ACL_INIT_QUEUE, Save R2,R3,R4
MOVAB   @#CTL$GL_PCB, R3
MOVL    ORB_ADDRESS, ORB
BBS      #1, 11(ORB), 1$
MOVZWL   #65535, 4(ORB)
MOVAB    4(ORB), R0
MOVL     CTL$GL_PCB, R4
JSB      @#SCH$LOCKW
BISB2    #2, 11(ORB)
MOVAB    40(ORB), R0
MOVL     R0, 44(ORB)
MOVL     R0, 40(ORB)
MOVAB    4(ORB), R0
MOVL     CTL$GL_PCB, R4
JSB      @#SCH$UNLOCK
MTPR     #0, #18
MOVL     #1, R0
RET

```

```

33      0B      53 00000000G 9F 001C 00000
      04      52      04 AC D0 00009
      04      A2      FFFF 8F 3C 00012
      50      04 A2 9E 00018
      54      00000000G 9F 16 0001F
      0B      A2      28 02 88 00025
      2C      50      28 A2 9E 00029
      28      A2      50 D0 0002D
      50      04 A2 9E 00035
      54      00000000G 9F 16 0003C
      12      00 DA 00042
      50      01 D0 00045 1$:
      04 00048

```

```

: 1103
: 1159
: 1160
: 1163
: 1164
: 1165
: 1166
: 1167
: 1168
: 1171
: 1173

```

; Routine Size: 73 bytes, Routine Base: \$CODE\$ + 0000

ACL_ADDENTRY - add an ACE to an ACL

```
186 1174 1 %SBTTL 'ACL_ADDENTRY - add an ACE to an ACL'
187 1175 1 GLOBAL ROUTINE ACL_ADDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER) =
188 1176 1
189 1177 1 !++
190 1178 1
191 1179 1 FUNCTIONAL DESCRIPTION:
192 1180 1
193 1181 1 This routine is used to add an Access Control Entry to the file ACL.
194 1182 1 If the ACL context is zero, the ACE is added to the beginning of the
195 1183 1 ACL. Otherwise, it is inserted into the ACL at the selected place.
196 1184 1
197 1185 1 It should be noted that adding an ACE anywhere in the ACL other than
198 1186 1 the end could possibly result in corruption of the ACL if the system
199 1187 1 should crash while the new ACE is being inserted.
200 1188 1
201 1189 1 CALLING SEQUENCE:
202 1190 1 ACL_ADDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER)
203 1191 1
204 1192 1 INPUT PARAMETERS:
205 1193 1 ACL_QUEUE_HEAD: address of queue header for ACL
206 1194 1 ACL_CONTEXT: address of ACL context longword
207 1195 1 LENGTH: size of the user Access Control Entry
208 1196 1 ACE_BUFFER: address of the user Access Control Entry
209 1197 1
210 1198 1 IMPLICIT INPUTS:
211 1199 1 NONE
212 1200 1
213 1201 1 OUTPUT PARAMETERS:
214 1202 1 NONE
215 1203 1
216 1204 1 IMPLICIT OUTPUTS:
217 1205 1 NONE
218 1206 1
219 1207 1 ROUTINE VALUE:
220 1208 1 1
221 1209 1
222 1210 1 SIDE EFFECTS:
223 1211 1 Access Control Entry inserted in or appended to the file ACL. If
224 1212 1 it is an insertion, the ACL context is updated to point after the
225 1213 1 inserted ACE.
226 1214 1
227 1215 1 !--
228 1216 1
229 1217 2 BEGIN
230 1218 2
231 1219 2 MAP
232 1220 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
233 1221 2 ACL_CONTEXT : REF $BBLOCK; ! Context longword
234 1222 2
235 1223 2 LABEL
236 1224 2 ADD_ENTRY; ! Add one ACE to the ACL
237 1225 2
238 1226 2 LOCAL
239 1227 2 COUNT, ! Length of remaining buffer
240 1228 2 ACE : REF $BBLOCK, ! The address of the user ACE
241 1229 2 ACL_POINTER : REF $BBLOCK, ! Pointer to current ACL segment
242 1230 2 ACL_SPLIT : REF $BBLOCK, ! Offset to current ACE
```

; R

```
243 1231 2      ACE_POINTER      : REF $BBLOCK,      ! Pointer to current ACE
244 1232 2      ACE_NUMBER,      ! Index of ACE in ACL
245 1233 2      ACL_LENGTH,      ! Length of all ACE's in segment
246 1234 2      NEW_ACL          : REF $BBLOCK,      ! Address of the new ACL segment
247 1235 2      OLD_CONTEXT      : $BBLOCK [4];      ! Index of existing ACL entry
248 1236 2
249 1237 2
250 1238 2      ! The ACE buffer may contain multiple ACEs. Loop over the ACEs in the buffer,
251 1239 2      ! adding them one at a time.
252 1240 2
253 1241 2      COUNT = .LENGTH;
254 1242 2      ACE = .ACE_BUFFER;
255 1243 2      UNTIL .COUNT LEQ 0
256 1244 2      DO
257 1245 3          BEGIN
258 1246 4              ADD_ENTRY: BEGIN
259 1247 4
260 1248 4      ! Sanity check the contents of the ACE - make sure the count field does
261 1249 4      ! not exceed the remaining buffer, and that the ACE is at least 4 bytes long.
262 1250 4
263 1251 4          IF .COUNT LSSU 4
264 1252 4          THEN RETURN SSS_BADPARAM;
265 1253 4
266 1254 4          IF .ACE[ACESB_SIZE] GTR .COUNT
267 1255 4          OR .ACE[ACESB_SIZE] EQL 0
268 1256 4          THEN ACL_ERROR (SSS_IVACL);
269 1257 4
270 1258 4      ! If the ACE being added is an AUDIT or ALARM ACE, force it to the beginning
271 1259 4      ! of the ACL.
272 1260 4
273 1261 4          ACE_NUMBER = .ACL_CONTEXT[CONTEXT_INDEX];
274 1262 4          IF .ACE[ACESB_TYPE] EQL ACESC_AUDIT
275 1263 4          OR .ACE[ACESB_TYPE] EQL ACESC_ALARM
276 1264 4          THEN ACE_NUMBER = 0;
277 1265 4
278 1266 4      ! Determine if the ACE exists already. If it does, the result depends on
279 1267 4      ! the relative position of the old and new ACEs. Effectively, we remove
280 1268 4      ! the one that is masked by the one preceding it in the ACL.
281 1269 4
282 1270 4          IF ACL_FINDENTRY (.ACL_QUEUE_HEAD, OLD_CONTEXT, .ACE[ACESB_SIZE], .ACE, 1)
283 1271 4          THEN
284 1272 5              BEGIN
285 1273 5                  IF .OLD_CONTEXT[CONTEXT_INDEX] LSSU .ACE_NUMBER
286 1274 5                  THEN LEAVE ADD_ENTRY;
287 1275 5                  ACL_DEENTRY (.ACL_QUEUE_HEAD, OLD_CONTEXT, 0, 0);
288 1276 4                  END;
289 1277 4
290 1278 4      ! Now locate the appropriate ACL segment. If there is no ACL
291 1279 4      ! as yet, simply allocate a block of memory and build
292 1280 4      ! the new ACL.
293 1281 4
294 1282 4          IF .ACL_QUEUE_HEAD[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
295 1283 4          THEN
296 1284 5              BEGIN
297 1285 5                  ACL_POINTER = ALLOC_PAGED (ACL$C_LENGTH + .ACE[ACESB_SIZE], ACL_TYPE);
298 1286 5                  CH$MOVE (.ACE[ACESB_SIZE], .ACE, ACL_POINTER[ACL$LIST]);
299 1287 5                  ACL_POINTER[ACL$W_SIZE] = ACL$C_LENGTH + .ACE[ACESB_SIZE];
```



```

300 1288 5      INSQUE (.ACL_POINTER, .ACL_QUEUE_HEAD[ACL$FLINK]);
301 1289 5      ACE_NUMBER = 1;
302 1290 5      END
303 1291 5
304 1292 5      ! If there is an existing ACL, position to the location indicated by the
305 1293 5      ! context. Then advance over any existing audit or alarm ACEs to ensure
306 1294 5      ! that they stay at the front of the ACL. Finally, if we are positioned
307 1295 5      ! at the start of a segment, back up to the end of the previous. This prevents
308 1296 5      ! successive additions at the same point from fragmenting the ACL.
309 1297 5
310 1298 4      ELSE
311 1299 5          BEGIN
312 1300 5              ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACE_NUMBER, ACL_POINTER, ACL_SPLIT);
313 1301 5              ACE_POINTER = ACL_POINTER[ACL$LIST] + .ACL_SPLIT;
314 1302 5              UNTIL ACL_POINTER[ACL$FLINK] EQA ACL_QUEUE_HEAD[ACL$FLINK]
315 1303 6                  OR (.ACE_POINTER[ACE$B_TYPE] NEQ ACE$C_AUDIT
316 1304 6                      AND .ACE_POINTER[ACE$B_TYPE] NEQ ACE$C_ALARM)
317 1305 5              DO
318 1306 6                  BEGIN
319 1307 6                      ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACE$B_SIZE];
320 1308 6                      ACE_NUMBER = .ACE_NUMBER + 1;
321 1309 6                      IF .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$W_SIZE]
322 1310 6                          THEN
323 1311 7                              BEGIN
324 1312 7                                  ACL_POINTER = .ACL_POINTER[ACL$FLINK];
325 1313 7                                  ACE_POINTER = ACL_POINTER[ACL$LIST];
326 1314 6                                  END;
327 1315 5                              END;
328 1316 5
329 1317 5                      IF .ACE_POINTER EQA ACL_POINTER[ACL$LIST]
330 1318 5                      AND .ACL_POINTER[ACL$BLINK] NEQA ACE_QUEUE_HEAD[ACL$FLINK]
331 1319 5                      THEN
332 1320 6                          BEGIN
333 1321 6                              ACL_POINTER = .ACL_POINTER[ACL$BLINK];
334 1322 6                              ACE_POINTER = .ACL_POINTER + .ACL_POINTER[ACL$W_SIZE];
335 1323 5                              END;
336 1324 5
337 1325 5      ! Now check the size of the segment. If the new entry still fits within
338 1326 5      ! the maximum segment size, insert it by allocating a new segment and
339 1327 5      ! copying in the pieces.
340 1328 5
341 1329 5          ACL_SPLIT = .ACE_POINTER - ACL_POINTER[ACL$LIST];
342 1330 5          ACL_LENGTH = .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH;
343 1331 5          IF .ACL_LENGTH + .ACE[ACE$B_SIZE] LEQU MAX_ACL_SIZE
344 1332 5              THEN
345 1333 6                  BEGIN
346 1334 6                      NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH + .ACE[ACE$B_SIZE], ACL_TYPE);
347 1335 6                      NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH + .ACE[ACE$B_SIZE];
348 1336 6                      ACE_POINTER = CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$LIST],
349 1337 6                                              NEW_ACL[ACL$LIST]);
350 1338 6                      ACE_POINTER = CH$MOVE (.ACE[ACE$B_SIZE], .ACE, .ACE_POINTER);
351 1339 6                      CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
352 1340 6                          ACL_POINTER[ACL$LIST] + .ACL_SPLIT, .ACE_POINTER);
353 1341 6                      INSQUE (.NEW_ACL, .ACL_POINTER[ACL$BLINK]);
354 1342 6                      END
355 1343 6
356 1344 6      ! Otherwise we have to split the segment. We put the new ACE in whichever
```

```

357 1345 6 ! segment is smaller. Because the max size of an ACE is 256, and the
358 1346 6 ! max segment size is 512, we are guaranteed that the new ACE will fit
359 1347 6 ! in one or the other (i.e., a 3-way split is not necessary).
360 1348 6
361 1349 5
362 1350 6
363 1351 6
364 1352 6
365 1353 7
366 1354 7
367 1355 7
368 1356 7
369 1357 7
370 1358 7
371 1359 7
372 1360 7
373 1361 7
374 1362 7
375 1363 7
376 1364 7
377 1365 7
378 1366 6
379 1367 7
380 1368 7
381 1369 7
382 1370 7
383 1371 7
384 1372 7
385 1373 7
386 1374 7
387 1375 7
388 1376 7
389 1377 7
390 1378 6
391 1379 5
392 1380 5
393 1381 5
394 1382 4
395 1383 4
396 1384 4
397 1385 4
398 1386 4
399 1387 4
400 1388 4
401 1389 4
402 1390 4
403 1391 3
404 1392 3
405 1393 3
406 1394 2
407 1395 2
408 1396 2
409 1397 2
410 1398 1

! segment is smaller. Because the max size of an ACE is 256, and the
! max segment size is 512, we are guaranteed that the new ACE will fit
! in one or the other (i.e., a 3-way split is not necessary).

ELSE
  BEGIN
    IF .ACL_SPLIT LEQU .ACL_LENGTH - .ACL_SPLIT
    THEN
      BEGIN
        NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT, ACL_TYPE);
        NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT;
        CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
                  ACL_POINTER[ACL$C_LIST] + .ACL_SPLIT, NEW_ACL[ACL$C_LIST]);
        INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
        NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_SPLIT + .ACE[ACE$B_SIZE], ACL_TYPE);
        NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_SPLIT + .ACE[ACE$B_SIZE];
        ACE_POINTER = CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$C_LIST],
                               NEW_ACL[ACL$C_LIST]);
        CH$MOVE (.ACE[ACE$B_SIZE], .ACE, .ACE_POINTER);
        INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
      END
    ELSE
      BEGIN
        NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT + .ACE[ACE$B_SIZE], ACL_TYPE);
        NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT + .ACE[ACE$B_SIZE];
        ACE_POINTER = CH$MOVE (.ACE[ACE$B_SIZE], .ACE, NEW_ACL[ACL$C_LIST]);
        CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
                  ACL_POINTER[ACL$C_LIST] + .ACL_SPLIT, .ACE_POINTER);
        INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
        NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_SPLIT, ACL_TYPE);
        NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_SPLIT;
        CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$C_LIST], NEW_ACL[ACL$C_LIST]);
        INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
      END;
    END;
    REMQUE (.ACL_POINTER, ACL_POINTER);
    DALLOC_PAGED (.ACL_POINTER, ACL_TYPE);
    END;

! At this point the ACE has been added to the ACL. Finish up by setting the
! ACL context.

    IF .ACE[ACE$B_TYPE] EQL ACE$C_AUDIT
    OR .ACE[ACE$B_TYPE] EQL ACE$C_ALARM
    THEN .ACL_CONTEXT = .ACL_CONTEXT + 1
    ELSE .ACL_CONTEXT = .ACE_NUMBER + 1;
    END;
    COUNT = .COUNT - .ACE[ACE$B_SIZE];
    ACE = .ACE + .ACE[ACE$B_SIZE];
    END;

    RETURN 1;

END;

! end of block ADD_ENTRY

! end of ACE processing loop

! End of routine ACL_ADDENTRY
```


				OFFC 00000	.ENTRY	ACL_ADDENTRY, Save R2,R3,R4,R5,R6,R7,R8,R9,-; R10,R11	
		5E		0C C2 00002	SUBL2	#12, SP	1175
		5B	0C	AC D0 00005	MOVL	LENGTH, COUNT	1241
		58	10	AC D0 00009	MOVL	ACE_BUFFER, ACE	1242
				5B D5 0000D 1\$:	TSTL	COUNT	1243
				03 14 0000F	BGTR	2\$	
			02A2	31 00011	BRW	23\$	
		04		5B D1 00014 2\$:	CMPL	COUNT, #4	1251
				04 1E 00017	BGEQU	3\$	
		50		14 D0 00019	MOVL	#20, R0	1252
				04 0001C	RET		
5B	68	08		00 ED 0001D 3\$:	CMPZV	#0, #8, (ACE), COUNT	1254
				04 14 00022	BGTR	4\$	
				68 95 00024	TSTB	(ACE)	1255
				12 12 00026	BNEQ	5\$	
5B	00	6E		00 2C 00028 4\$:	MOVCS	#0, (SP), #0, COUNT, (ACE)	1256
				68 0002D			
	02	A8	21E4	8F B0 0002E	MOVW	#8676, 2(ACE)	
		50	21E4	8F 3C 00034	MOVZWL	#8676, R0	
				04 00039	RET		
5A	08	BC		00 EF 0003A 5\$:	EXTZV	#0, #24, @ACL_CONTEXT, ACE_NUMBER	1261
		18		A8 91 00040	CMPB	1(ACE), #5	1262
		05	01	06 13 00044	BEQL	6\$	
		06	01	A8 91 00046	CMPB	1(ACE), #6	1263
				02 12 0004A	BNEQ	7\$	
				5A D4 0004C 6\$:	CLRL	ACE_NUMBER	1264
				01 DD 0004E 7\$:	PUSHL	#1	1270
				58 DD 00050	PUSHL	ACE	
		7E		68 9A 00052	MOVZBL	(ACE), -(SP)	
			0C	AE 9F 00055	PUSHAB	OLD_CONTEXT	
			04	AC DD 00058	PUSHL	ACL_QUEUE_HEAD	
		0000V		05 FB 0005B	CALLS	#5, ACL_FINDENTRY	
		CF		50 E9 00060	BLBC	R0, 9\$	
5A	6E	18		00 ED 00063	CMPZV	#0, #24, OLD_CONTEXT, ACE_NUMBER	1273
				03 1E 00068	BGEQU	8\$	
			023A	31 0006A	BRW	22\$	
				7E 7C 0006D 8\$:	CLRQ	-(SP)	1275
			08	AE 9F 0006F	PUSHAB	OLD_CONTEXT	
			04	AC DD 00072	PUSHL	ACL_QUEUE_HEAD	
		0000V		04 FB 00075	CALLS	#4, ACL_DELENTY	
		04		BC D1 0007A 9\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	1282
				3A 12 0007F	BNEQ	10\$	
				07 DD 00081	PUSHL	#7	1285
		7E		68 9A 00083	MOVZBL	(ACE), -(SP)	
		6E		0C C0 00086	ADDL2	#12, (SP)	
		00		02 FB 00089	CALLS	#2, ALLOC PAGED	
	00000000G	AE		50 D0 00090	MOVL	R0, ACL_POINTER	
	08	51		68 9A 00094	MOVZBL	(ACE), R1	1286
		50	08	AE D0 00097	MOVL	ACL_POINTER, R0	
		68		51 28 0009B	MOVCS	R1, -(ACE), 12(R0)	
0C	A0	50	08	AE D0 000A0	MOVL	ACL_POINTER, R0	1287
		08		68 9B 000A4	MOVZBW	(ACE), 8(R0)	
		08		A0 000A8	ADDW2	#12, 8(R0)	
		50	04	BC 9E 000AC	MOVAB	@ACL_QUEUE_HEAD, R0	1288

00	B0	08	BE	0E	000B0	INSQUE	@ACL_POINTER, @0(R0)	:	1289
	5A		01	D0	000B5	MOVL	#1, ACE_NUMBER	:	1282
		01	D6	31	000B8	BRW	19\$:	1300
		04	AE	9F	000BB	PUSHAB	ACL_SPLIT	:	
		0C	AE	9F	000BE	PUSHAB	ACL_POINTER	:	
			5A	DD	000C1	PUSHL	ACE_NUMBER	:	
		04	AC	DD	000C3	PUSHL	ACL_QUEUE_HEAD	:	
	0000V		04	04	FB	CALLS	#4, ACL_LOCATEACE	:	
			50	D0	000CB	MOVL	R0, ACE_NUMBER	:	
53	08	04	AE	C1	000CE	ADDL3	ACL_SPLIT, ACL_POINTER, R3	:	1301
		0C	A3	9E	000D4	MOVAB	12(R3), ACE_POINTER	:	
		08	AE	D0	000D8	MOVL	ACL_POINTER, R0	:	1302
	04		50	D1	000DC	CMPL	R0, ACL_QUEUE_HEAD	:	
			2B	13	000E0	BEQL	13\$:	
		01	A9	91	000E2	CMPB	1(ACE_POINTER), #5	:	1303
			06	13	000E6	BEQL	12\$:	
		01	A9	91	000E8	CMPB	1(ACE_POINTER), #6	:	1304
			1F	12	000EC	BNEQ	13\$:	
			69	9A	000EE	MOVZBL	(ACE_POINTER), R1	:	1307
			51	C0	000F1	ADDL2	R1, ACE_POINTER	:	
			5A	D6	000F4	INCL	ACE_NUMBER	:	1308
		08	A0	3C	000F6	MOVZWL	8(R0), R1	:	1309
			50	C0	000FA	ADDL2	R0, R1	:	
			59	D1	000FD	CMPL	ACE_POINTER, R1	:	
			D6	1F	00100	BLSSU	11\$:	
	08		60	D0	00102	MOVL	(R0), ACL_POINTER	:	1312
59	08		0C	C1	00106	ADDL3	#12, ACL_POINTER, ACE_POINTER	:	1313
			CB	11	0010B	BRB	11\$:	1302
		08	AE	D0	0010D	MOVL	ACL_POINTER, R0	:	1317
		0C	A0	9E	00111	MOVAB	12(R0), R1	:	
			59	D1	00115	CMPL	ACE_POINTER, R1	:	
			17	12	00118	BNEQ	14\$:	
	04	AC	04	A0	D1	CMPL	4(R0), ACL_QUEUE_HEAD	:	1318
			10	13	0011F	BEQL	14\$:	
	08	AE	04	A0	D0	MOVL	4(R0), ACL_POINTER	:	1321
		50	08	AE	D0	MOVL	ACL_POINTER, R0	:	1322
		59	08	A0	3C	MOVZWL	8(R0), ACE_POINTER	:	
		59		50	C0	ADDL2	R0, ACE_POINTER	:	
		50	08	AE	D0	MOVL	ACL_POINTER, R0	:	1329
53		59		50	C3	SUBL3	R0, ACE_POINTER, R3	:	
	04	AE	F4	A3	9E	MOVAB	-12(R3), ACL_SPLIT	:	
		56	08	A0	3C	MOVZWL	8(R0), ACL_LENGTH	:	1330
		56		0B	C2	SUBL2	#11, ACL_LENGTH	:	
		53		68	9A	MOVZBL	(ACE), R3	:	1331
		52	76	43	9E	MOVAB	-(ACL_LENGTH)[R3], R2	:	
00000200		8F		52	D1	CMPL	R2, #512	:	
				4E	1A	BGTRU	15\$:	
				07	DD	PUSHL	#7	:	1334
		0C	A2	9F	00157	PUSHAB	12(R2)	:	
00000000G	00		02	FB	0015A	CALLS	#2, ALLOC PAGED	:	
	57		50	D0	00161	MOVL	R0, NEW_ACL	:	
	50		68	9A	00164	MOVZBL	(ACE), R0	:	1335
	51	0C	A0	46	9E	MOVAB	12(R0)[ACL_LENGTH], R1	:	
			51	B0	0016C	MOVW	R1, 8(NEW_ACL)	:	
	08	A7	08	AE	D0	MOVL	ACL_POINTER, R0	:	1336
0C	A7	0C	04	AE	28	MOVCL3	ACL_SPLIT, 12(R0), 12(NEW_ACL)	:	1337
			53	D0	0017B	MOVL	R3, ACE_POINTER	:	

69		50	68	9A 0017E	MOVZBL	(ACE), R0	1338
		68	50	28 00181	MOVCL3	R0, (ACE), (ACE_POINTER)	
		59	53	D0 00185	MOVL	R3, ACE_POINTER	
52		56	04	AE C3 00188	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1339
50	08	AE	04	AE C1 0018D	ADDL3	ACL_SPLIT, ACL_POINTER, R0	1340
69	OC	A0		52 28 00193	MOVCL3	R2, 12(R0), (ACE_POINTER)	
		50	08	AE D0 00198	MOVL	ACL_POINTER, R0	1341
	04	B0		67 0E 0019C	INSQUE	(NEW_ACL), @4(R0)	
			00DD	31 001A0	BRW	18\$	1331
52		56	04	AE C3 001A3	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1354
		52		OC C0 001A8	ADDL2	#12, R2	
50		56	04	AE C3 001AB	SUBL3	ACL_SPLIT, ACL_LENGTH, R0	1351
		50	04	AE D1 001B0	CMP	ACL_SPLIT, R0	
				66 1A 001B4	BGTRU	16\$	
				07 DD 001B6	PUSHL	#7	1354
				52 DD 001B8	PUSHL	R2	
	00000000G	00		02 FB 001BA	CALLS	#2, ALLOC_PAGED	
		57		50 D0 001C1	MOVL	R0, NEW_ACL	
08	52	56	04	AE C3 001C4	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1355
	A7	52		OC A1 001C9	ADDW3	#12, R2, 8(NEW_ACL)	
	52	56	04	AE C3 001CE	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1356
OC	50	AE	04	AE C1 001D3	ADDL3	ACL_SPLIT, ACL_POINTER, R0	1357
	A7	A0		52 28 001D9	MOVCL3	R2, 12(R0), 12(NEW_ACL)	
		BE		67 0E 001DF	INSQUE	(NEW_ACL), @ACL_POINTER	1358
				07 DD 001E3	PUSHL	#7	1359
		50		68 9A 001E5	MOVZBL	(ACE), R0	
		50	08	AE C0 001E8	ADDL2	ACL_SPLIT, R0	
			OC	A0 9F 001EC	PUSHAB	12(R0)	
	00000000G	00		02 FB 001EF	CALLS	#2, ALLOC_PAGED	
		57		50 D0 001F6	MOVL	R0, NEW_ACL	
		50		68 9A 001F9	MOVZBL	(ACE), R0	1360
08	A7	50	04	AE C0 001FC	ADDL2	ACL_SPLIT, R0	
		50		OC A1 00200	ADDW3	#12, R0, 8(NEW_ACL)	
OC	A7	50	08	AE D0 00205	MOVL	ACL_POINTER, R0	1361
		A0	04	AE 28 00209	MOVCL3	ACL_SPLIT, 12(R0), 12(NEW_ACL)	1362
		59		53 D0 00210	MOVL	R3, ACE_POINTER	
		50		68 9A 00213	MOVZBL	(ACE), R0	1363
69		68		50 28 00216	MOVCL3	R0, (ACE), (ACE_POINTER)	
				60 11 0021A	BRB	17\$	1364
				07 DD 0021C	PUSHL	#7	1368
	00000000G	00	6342	9F 0021E	PUSHAB	(R3)[R2]	
		57		02 FB 00221	CALLS	#2, ALLOC_PAGED	
52		56	04	AE C3 00228	MOVL	R0, NEW_ACL	
		50		68 9A 0022B	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1369
		52		50 C0 00233	MOVZBL	(ACE), R0	
08	A7	52		OC A1 00236	ADDL2	R0, R2	
		50		68 9A 0023B	ADDW3	#12, R2, 8(NEW_ACL)	
OC	A7	68		50 28 0023E	MOVZBL	(ACE), R0	1370
		59		53 D0 00243	MOVCL3	R0, (ACE), 12(NEW_ACL)	
52		56	04	AE C3 00246	MOVL	R3, ACE_POINTER	1371
50	08	AE	04	AE C1 0024B	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1372
69	OC	A0		52 28 00251	ADDL3	ACL_SPLIT, ACL_POINTER, R0	
	08	BE		67 0E 00256	MOVCL3	R2, 12(R0), (ACE_POINTER)	
				07 DD 0025A	INSQUE	(NEW_ACL), @ACL_POINTER	1373
7E	08	AE		OC C1 0025C	PUSHL	#7	1374
	00000000G	00		02 FB 00261	ADDL3	#12, ACL_SPLIT, -(SP)	
					CALLS	#2, ALLOC_PAGED	

ACL_ADDENTRY - add an ACE to an ACL

B 14
15-Sep-1984 23:51:08
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[F11X.SRC]ACLSUBR.B32;1

08	A7	04	57	50	D0	00268	MOVL	R0, NEW_ACL	1375
			AE	0C	A1	0026B	ADDW3	#12, ACC_SPLIT, 8(NEW_ACL)	1376
0C	A7	0C	50	08	AE	D0 00271	MOVL	ACL_POINTER, R0	1377
		08	A0	04	AE	28 00275	MOV3	ACL_SPLIT, 12(R0), 12(NEW_ACL)	1380
		08	BE	08	67	0E 0027C	INSQUE	(NEW_ACL), @ACL_POINTER	1381
		08	AE	08	BE	0F 00280	REMQUE	@ACL_POINTER, ACL_POINTER	1387
				0C	07	DD 00285	PUSHL	#7	1388
	00000000G	00		0C	AE	DD 00287	PUSHL	ACL_POINTER	1389
		05		01	02	FB 0028A	CALLS	#2, DALLOC_PAGED	1390
		06		01	A8	91 00291	CMPB	1(ACE), #5	1392
				01	06	13 00295	BEQL	20\$	1393
				01	A8	91 00297	CMPB	1(ACE), #6	1243
				08	05	12 0029B	BNEQ	21\$	1396
				08	BC	D6 0029D	INCL	@ACL_CONTEXT	1398
				01	05	11 002A0	BRB	22\$	
	08	BC		01	AA	9E 002A2	MOVAB	1(R10), @ACL_CONTEXT	
		50			68	9A 002A7	MOVZBL	(ACE), R0	
		5B			50	C2 002AA	SUBL2	R0, COUNT	
		50			68	9A 002AD	MOVZBL	(ACE), R0	
		58			50	C0 002B0	ADDL2	R0, ACE	
				FD57	31	002B3	BRW	1\$	
		50		01	D0	002B6	MOVL	#1, R0	
				04	002B9		RET		

; Routine Size: 698 bytes, Routine Base: \$CODE\$ + 0049


```

412 1399 1 %SBTTL 'ACL DELENTY - remove an ACE from an ACL'
413 1400 1 GLOBAL ROUTINE ACL_DELENTY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE) =
414 1401 1
415 1402 1 ++
416 1403 1
417 1404 1 FUNCTIONAL DESCRIPTION:
418 1405 1
419 1406 1 This routine is used to delete an Access Control Entry from a file ACL.
420 1407 1 If the ACL context is valid, and no ACE is specified, then the ACE
421 1408 1 pointed to by the context is removed. If an ACE is specified,
422 1409 1 regardless of the ACL context, it is first located and then removed.
423 1410 1
424 1411 1 CALLING SEQUENCE:
425 1412 1 ACL_DELENTY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE)
426 1413 1
427 1414 1 INPUT PARAMETERS:
428 1415 1 ACL_QUEUE_HEAD: address of queue header for ACL
429 1416 1 ACL_CONTEXT: address of ACL context longword
430 1417 1 COUNT: size of the user Access Control Entry
431 1418 1 ACE: address of the user Access Control Entry
432 1419 1
433 1420 1 IMPLICIT INPUTS:
434 1421 1 NONE
435 1422 1
436 1423 1 OUTPUT PARAMETERS:
437 1424 1 NONE
438 1425 1
439 1426 1 IMPLICIT OUTPUTS:
440 1427 1 NONE
441 1428 1
442 1429 1 ROUTINE VALUE:
443 1430 1 1
444 1431 1
445 1432 1 SIDE EFFECTS:
446 1433 1 The Specified ACE is removed from the ACL. If the ACL segment is then
447 1434 1 empty, it is removed from the chain. The ACL context is updated to
448 1435 1 point to the next ACE in the ACL.
449 1436 1
450 1437 1 --
451 1438 1
452 1439 2 BEGIN
453 1440 2
454 1441 2 MAP
455 1442 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
456 1443 2 ACL_CONTEXT : REF $BBLOCK, ! Context longword
457 1444 2 ACE : REF $BBLOCK; ! Address of the user ACE
458 1445 2
459 1446 2 LOCAL
460 1447 2 ACL_POINTER : REF $BBLOCK, ! Pointer to current ACL segment
461 1448 2 ACL_SPLIT : REF $BBLOCK, ! Offset to current ACE
462 1449 2 ACE_POINTER : REF $BBLOCK, ! Pointer to current ACE
463 1450 2 ACE_NUMBER, ! Index of ACE in ACL
464 1451 2 ACL_LENGTH, ! Length of all ACE's in segment
465 1452 2 NEW_ACL : REF $BBLOCK; ! Address of the new ACL segment
466 1453 2
467 1454 2
468 1455 2 ! Sanity check the length of the supplied ACE.
```



```

: 469 1456 2
: 470 1457 2 IF .COUNT LSSU 4
: 471 1458 2 AND .COUNT NEQ 0
: 472 1459 2 THEN RETURN SSS_BADPARAM;
: 473 1460 2
: 474 1461 2 ! Locate the ACE by content if the content is specified. Note that this
: 475 1462 2 ! will change the context.
: 476 1463 2
: 477 1464 2 IF .ACL_QUEUE_HEAD[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
: 478 1465 2 THEN ACL_ERROR (SSS_ACLEMPY);
: 479 1466 2
: 480 1467 2 IF .COUNT NEQ 0
: 481 1468 2 THEN IF NOT ACL_FINDENTRY (.ACL_QUEUE_HEAD, .ACL_CONTEXT, .COUNT, .ACE, 1)
: 482 1469 2 THEN ACL_ERROR (SSS_NOENTRY);
: 483 1470 2
: 484 1471 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX], ACL_POINTER, ACL_SPLIT);
: 485 1472 2 ACE_POINTER = ACL_POINTER[ACL$LIST] + .ACL_SPLIT;
: 486 1473 2
: 487 1474 2 ! Having located the ACE, compute the length of the remaining segment.
: 488 1475 2 ! If it is non-null, allocate a new segment and copy in the remaining
: 489 1476 2 ! portions of the old one. Finally deallocate the old segment.
: 490 1477 2
: 491 1478 2 ACL_LENGTH = .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH - .ACE_POINTER[ACE$B_SIZE];
: 492 1479 2 IF .ACL_LENGTH NEQ 0
: 493 1480 2 THEN
: 494 1481 3 BEGIN
: 495 1482 3 NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH, ACL_TYPE);
: 496 1483 3 NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH;
: 497 1484 3 CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$LIST], NEW_ACL[ACL$LIST]);
: 498 1485 3 CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
: 499 1486 3 ACL_POINTER[ACL$LIST] + .ACL_SPLIT + .ACE_POINTER[ACE$B_SIZE],
: 500 1487 3 NEW_ACL[ACL$LIST] + .ACL_SPLIT);
: 501 1488 3 INSQUE (.NEW_ACL, .ACL_POINTER[ACL$BLINK]);
: 502 1489 2 END;
: 503 1490 2
: 504 1491 2 REMQUE (.ACL_POINTER, ACL_POINTER);
: 505 1492 2 DALLOC_PAGED (.ACL_POINTER, ACL_TYPE);
: 506 1493 2
: 507 1494 2 RETURN 1;
: 508 1495 2
: 509 1496 1 END;
```

! End of routine ACL_DELENTY

				01FC 00000	.ENTRY	ACL_DELENTY, Save R2,R3,R4,R5,R6,R7,R8	: 1400
	5E			08 C2 00002	SUBL2	#8, SP	
	04	0C		AC D1 00005	CMPL	COUNT, #4	: 1457
				09 1E 00009	BGEQU	1\$	
		0C		AC D5 0000B	TSTL	COUNT	: 1458
				04 13 0000E	BEQL	1\$	
	50			14 D0 00010	MOVL	#20, R0	: 1459
				04 00013	RET		
	04	AC	04	BC D1 00014 1\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	: 1464
				18 12 00019	BNEQ	2\$	
0C	AC		00	6E 00 2C 0001B	MOVCS	#0, (SP), #0, COUNT, @ACE	: 1465

PC	AC	BC	DE	HL	SP	DP	AP	IP	OP	Comment	Address	
		02	50	10	BC	00021				MOVL	ACE, R0	1467
			A0	10	AC	00023				MOVW	#2512, 2(R0)	1468
			50	09D0	8F	B0 00027				MOVZWL	#2512, R0	
				09D0	8F	3C 0002D				RET		
					04	00032			2\$:	TSTL	COUNT	
				0C	AC	D5 00033				BEQL	3\$	
			7E		2A	13 00036				PUSHL	#1	
			7E	0C	AC	7D 0003A				MOVQ	COUNT, -(SP)	
			CF	04	AC	7D 0003E				MOVQ	ACL_QUEUE_HEAD, -(SP)	
		0000V	18		05	FB 00042				CALLS	#5, ACL_FINDENTRY	
			6E		50	EB 00047				BLBS	R0, 3\$	1469
0C	AC	00			00	2C 0004A				MOVCS	#0, (SP), #0, COUNT, @ACE	
			50	10	BC	00050						
		02	A0	10	AC	D0 00052				MOVL	ACE, R0	
			50	09D8	8F	B0 00056				MOVW	#2520, 2(R0)	
				09D8	8F	3C 0005C				MOVZWL	#2520, R0	
					04	00061				RET		
					5E	DD 00062			3\$:	PUSHL	SP	1471
			18	08	AE	9F 00064				PUSHAB	ACL_POINTER	
					00	EF 00067				EXTZV	#0, #24, @ACL_CONTEXT, -(SP)	
7E	08	BC		04	AC	DD 0006D				PUSHL	ACL_QUEUE_HEAD	
			CF	04	AE	FB 00070				CALLS	#4, ACL LocateACE	1472
		0000V	56	04	AE	D0 00075				MOVL	ACL_POINTER, R6	
			56		6E	C1 00079				ADDL3	ACL_SPLIT, R6, R7	
		57	56		0C	C0 0007D				ADDL2	#12, ACE_POINTER	1478
			56	08	A6	3C 00080				MOVZWL	8(R6), R6	
			50		67	9A 00084				MOVZBL	(ACE_POINTER), R0	
			56		50	C2 00087				SUBL2	R0, R6	
			56		0C	C2 0008A				SUBL2	#12, ACL_LENGTH	1479
					3C	13 0008D				BEQL	4\$	1482
					07	DD 0008F				PUSHL	#7	
				0C	A6	9F 00091				PUSHAB	12(ACL_LENGTH)	
		00000000G	00		02	FB 00094				CALLS	#2, ALLOC_PAGED	
			58		50	D0 0009B				MOVL	R0, NEW_ACL	1483
08	A8		56		0C	A1 0009E				ADDW3	#12, ACL_LENGTH, 8(NEW_ACL)	1484
			50	04	AE	D0 000A3				MOVL	ACL_POINTER, R0	
0C	A8	0C	A0		6E	28 000A7				MOVCS	ACL_SPLIT, 12(R0), 12(NEW_ACL)	1485
			56		6E	C2 000AD				SUBL2	ACL_SPLIT, R6	1486
	51	04	AE		6E	C1 000B0				ADDL3	ACL_SPLIT, ACL_POINTER, R1	
			52		67	9A 000B5				MOVZBL	(ACE_POINTER), R2	1487
	50		58		6E							

; Routine Size: 224 bytes, Routine Base: \$CODE\$ + 0303


```

511 1497 1 %SBTTL 'ACL_MODENTRY - modify an existing ACE'
512 1498 1 GLOBAL ROUTINE ACL_MODENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE) =
513 1499 1
514 1500 1 ++
515 1501 1
516 1502 1 FUNCTIONAL DESCRIPTION:
517 1503 1
518 1504 1 This routine is used to replace an Access Control Entry in a file ACL.
519 1505 1 The entry pointed to by the context is replaced with the ACE given.
520 1506 1
521 1507 1 CALLING SEQUENCE:
522 1508 1 ACL_MODENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE)
523 1509 1
524 1510 1 INPUT PARAMETERS:
525 1511 1 ACL_QUEUE_HEAD: address of queue header for ACL
526 1512 1 ACL_CONTEXT: address of ACL context longword
527 1513 1 COUNT: size of the user Access Control Entry
528 1514 1 ACE: address of the user Access Control Entry
529 1515 1
530 1516 1 IMPLICIT INPUTS:
531 1517 1 NONE
532 1518 1
533 1519 1 OUTPUT PARAMETERS:
534 1520 1 NONE
535 1521 1
536 1522 1 IMPLICIT OUTPUTS:
537 1523 1 NONE
538 1524 1
539 1525 1 ROUTINE VALUE:
540 1526 1 1
541 1527 1
542 1528 1 SIDE EFFECTS:
543 1529 1 The ACE is replaced with the new one. This is done by deleting the
544 1530 1 ACE pointed to by the context and then inserting (adding) the
545 1531 1 changed ACE.
546 1532 1
547 1533 1 --
548 1534 1
549 1535 2 BEGIN
550 1536 2
551 1537 2 MAP
552 1538 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
553 1539 2 ACL_CONTEXT : REF $BBLOCK, ! Context longword
554 1540 2 ACE : REF $BBLOCK, ! Address of user supplied ACE
555 1541 2
556 1542 2 LOCAL
557 1543 2 ACL_POINTER : REF $BBLOCK, ! Pointer to current ACL segment
558 1544 2 ACL_SPLIT : REF $BBLOCK, ! Offset to current ACE
559 1545 2 ACE_POINTER : REF $BBLOCK, ! Pointer to current ACE
560 1546 2 ACE_NUMBER; ! Index of ACE in ACL
561 1547 2
562 1548 2
563 1549 2 ! Sanity check the length of the supplied ACE.
564 1550 2
565 1551 2 IF .COUNT LSSU 4
566 1552 2 THEN RETURN $$$_BADPARAM;
567 1553 2
```



```
: 568 1554 2 ! Check for something in the ACL.
: 569 1555 2
: 570 1556 2 IF .ACL_QUEUE_HEAD[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
: 571 1557 2 THEN ACL_ERROR (SS$_ACEMPTY);
: 572 1558 2
: 573 1559 2 ! Now locate the ACE to be modified.
: 574 1560 2
: 575 1561 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX], ACL_POINTER, ACL_SPLIT);
: 576 1562 2 IF .ACL_POINTER[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
: 577 1563 2 AND .ACL_SPLIT EQL .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH
: 578 1564 2 THEN ACL_ERROR (SS$_NOENTRY);
: 579 1565 2
: 580 1566 2 ! Remove the old ACE by context.
: 581 1567 2
: 582 1568 2 ACL_DELENTY (.ACL_QUEUE_HEAD, .ACL_CONTEXT, 0, 0);
: 583 1569 2
: 584 1570 2 ! Insert the new ACE.
: 585 1571 2
: 586 1572 2 ACL_ADDENTRY (.ACL_QUEUE_HEAD, .ACL_CONTEXT, .COUNT, .ACE);
: 587 1573 2
: 588 1574 2 RETURN 1;
: 589 1575 2
: 590 1576 1 END;
```

! End of routine ACL_MODENTRY

				003C 00000	.ENTRY	ACL_MODENTRY, Save R2,R3,R4,R5	: 1498
		5E		08 C2 00002	SUBL2	#8, SP	
		04	0C	AC D1 00005	CMPL	COUNT, #4	: 1551
				04 1E 00009	BGEQU	1\$	
		50		14 D0 0000B	MOVL	#20, R0	: 1552
				04 0000E	RET		
		04	AC	04 BC D1 0000F 1\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	: 1556
				18 12 00014	BNEQ	2\$	
OC	AC		00	6E 00 2C 00016	MOVC5	#0, (SP), #0, COUNT, @ACE	: 1557
				10 BC 0001C			
		50	10	AC D0 0001E	MOVL	ACE, R0	
		02	A0	09D0 8F B0 00022	MOVW	#2512, 2(R0)	
		50	09D0	8F 3C 00028	MOVZWL	#2512, R0	
				04 0002D	RET		
				5E DD 0002E 2\$:	PUSHL	SP	: 1561
			08	AE 9F 00030	PUSHAB	ACL_POINTER	
		7E	08	BC 00 EF 00033	EXTZV	#0, #24, @ACL_CONTEXT, -(SP)	
				04 AC DD 00039	PUSHL	ACL_QUEUE_HEAD	
		0000V	CF	04 FB 0003C	CALLS	#4, ACL_LOCATEACE	
		50	04	AE D0 00041	MOVL	ACL_POINTER, R0	: 1562
		04	AC	60 D1 00045	CMPL	(R0), ACL_QUEUE_HEAD	
				24 12 00049	BNEQ	3\$	
		50	08	A0 3C 0004B	MOVZWL	8(R0), R0	: 1563
		50		0C C2 0004F	SUBL2	#12, R0	
		50		6E D1 00052	CMPL	ACL_SPLIT, R0	
				18 12 00055	BNEQ	3\$	
OC	AC		00	6E 00 2C 00057	MOVC5	#0, (SP), #0, COUNT, @ACE	: 1564
			10	BC 0005D			
		50	10	AC D0 0005F	MOVL	ACE, R0	

ACLSUBR
V04-000

ACL_MODENTRY - modify an existing ACE

H 14
15-Sep-1984 23:51:08
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[F11X.SRC]ACLSUBR.B32;1
Page 18
(5)

02	A0	09D8	8F	B0	00063	MOVW	#2520, 2(R0)	:	
	50	09D8	8F	3C	00069	MOVZWL	#2520, R0	:	
				04	0006E	RET		:	
			7E	7C	0006F	3\$: CLRQ	-(SP)	:	1568
FEA6	7E	04	AC	7D	00071	MOVQ	ACL_QUEUE HEAD, -(SP)	:	
	CF		04	FB	00075	CALLS	#4, -ACL_DELENTRY	:	
	7E	0C	AC	7D	0007A	MOVQ	COUNT, =(SP)	:	1572
	7E	04	AC	7D	0007E	MOVQ	ACL_QUEUE HEAD, -(SP)	:	
FBDF	CF		04	FB	00082	CALLS	#4, -ACL_ADDENTRY	:	
	50		01	D0	00087	MOVL	#1, R0	:	1574
			04	0008A	RET			:	1576

; Routine Size: 139 bytes, Routine Base: \$CODE\$ + 03E3

ACL_FINDENTRY - locate a specific ACE

```

592 1577 1 %SBTTL 'ACL_FINDENTRY - locate a specific ACE'
593 1578 1 GLOBAL ROUTINE ACL_FINDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL) =
594 1579 1
595 1580 1 ++
596 1581 1
597 1582 1 FUNCTIONAL DESCRIPTION:
598 1583 1
599 1584 1 This routine locates the specified Access Control Entry and sets the
600 1585 1 ACL context accordingly.
601 1586 1
602 1587 1 CALLING SEQUENCE:
603 1588 1 ACL_FINDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL)
604 1589 1
605 1590 1 INPUT PARAMETERS:
606 1591 1 ACL_QUEUE_HEAD: address of queue header for ACL
607 1592 1 ACL_CONTEXT: address of ACL context longword
608 1593 1 COUNT: size of the user Access Control Entry
609 1594 1 ACE: address of the user Access Control Entry
610 1595 1 INTERNAL: 0 call generated by a user request
611 1596 1 1 call generated within the system
612 1597 1
613 1598 1 IMPLICIT INPUTS:
614 1599 1 NONE
615 1600 1
616 1601 1 OUTPUT PARAMETERS:
617 1602 1 NONE
618 1603 1
619 1604 1 IMPLICIT OUTPUTS:
620 1605 1 NONE
621 1606 1
622 1607 1 ROUTINE VALUE:
623 1608 1 1 if successful
624 1609 1 0 otherwise
625 1610 1
626 1611 1 SIDE EFFECTS:
627 1612 1 NONE
628 1613 1
629 1614 1 --
630 1615 1
631 1616 2 BEGIN
632 1617 2
633 1618 2 MAP
634 1619 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
635 1620 2 ACL_CONTEXT : REF $BBLOCK, ! Context longword
636 1621 2 ACE : REF $BBLOCK; ! Address of user ACE
637 1622 2
638 1623 2 LOCAL
639 1624 2 ACL_POINTER : REF $BBLOCK, ! Pointer to current ACL segment
640 1625 2 ACL_SPLIT : REF $BBLOCK, ! Offset to current ACE
641 1626 2 ACE_POINTER : REF $BBLOCK, ! Pointer to current ACE
642 1627 2 ACE_NUMBER; ! Index of ACE in ACL
643 1628 2
644 1629 2
645 1630 2 ! Sanity check the length of the supplied ACE.
646 1631 2
647 1632 2 IF .COUNT LSSU 4
648 1633 2 THEN RETURN SS$_BADPARAM;
```

```

649 1634 2
650 1635 2 ! Check the length of the supplied ACE to make sure we've been given a
651 1636 2 ! complete buffer.
652 1637 2
653 1638 2 IF .ACE[ACESB_SIZE] GTRU .COUNT
654 1639 2 THEN ACL_ERROR (SS$_IVACL);
655 1640 2
656 1641 2 ! If there is no ACL present on the file, set the context to zero and return.
657 1642 2
658 1643 2 IF .ACL_QUEUE_HEAD[ACL$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$_FLINK]
659 1644 2 THEN
660 1645 2 BEGIN
661 1646 2 .ACL_CONTEXT = 0;
662 1647 2 IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$_ACLEMPY);
663 1648 2 END;
664 1649 2
665 1650 2 ! Loop through all of the ACL segments trying to locate the specified ACE.
666 1651 2
667 1652 2 ACE_NUMBER = 0;
668 1653 2 ACL_POINTER = ACL_QUEUE_HEAD[ACL$_FLINK];
669 1654 2 DO
670 1655 2 BEGIN
671 1656 2 ACL_POINTER = .ACL_POINTER[ACL$_FLINK];
672 1657 2 ACE_POINTER = ACL_POINTER[ACL$_LIST];
673 1658 2 UNTIL .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$_SIZE]
674 1659 2 DO
675 1660 2 BEGIN
676 1661 2 ACE_NUMBER = .ACE_NUMBER + 1;
677 1662 2
678 1663 2 ! How we match the ACE is type dependent. Generally speaking, ACEs match
679 1664 2 ! on the portion of their content by which they are selected in normal
680 1665 2 ! use.
681 1666 2
682 1667 2 IF
683 1668 2 BEGIN
684 1669 2 CASE .ACE[ACESB_TYPE] FROM ACESC_KEYID TO ACESC_DIRDEF OF
685 1670 2 SET
686 1671 2 [ACESC_BIJNL,
687 1672 2 ACESC_AIJNL,
688 1673 2 ACESC_ATJNL,
689 1674 2 ACESC_JNLID,
690 1675 2 ACESC_DIRDEF]:
691 1676 2 .ACE[ACESB_TYPE] EQL .ACE_POINTER[ACESB_TYPE];
692 1677 2
693 1678 2 [ACESC_INFO,
694 1679 2 INRANGE,
695 1680 2 OUTRANGE]:
696 1681 2 CH$EQL (.ACE[ACESB_SIZE], .ACE,
697 1682 2 .ACE_POINTER[ACESB_SIZE], .ACE_POINTER);
698 1683 2
699 1684 2 [ACESC_KEYID]:
700 1685 2 (.ACE AND NOT $FIELDMASK (ACESV_RESERVED)
701 1686 2 ^ ($BYTEOFFSET (ACESW_FLAGS)*8))
702 1687 2 EQL
703 1688 2 (.ACE_POINTER AND NOT $FIELDMASK (ACESV_RESERVED)
704 1689 2 ^ ($BYTEOFFSET (ACESW_FLAGS)*8))
705 1690 2
```



```

: 706      1691 5      AND CH$EQL (.ACE[ACESB_SIZE] - $BYTEOFFSET (ACESL_KEY)
: 707      1692 5      - .ACE[ACESV_RESERVED]*4,
: 708      1693 5      ACE[ACESL_KEY] + .ACE[ACESV_RESERVED]*4,
: 709      1694 5      .ACE_POINTER[ACESB_SIZE] - $BYTEOFFSET (ACESL_KEY)
: 710      1695 5      - .ACE_POINTER[ACESV_RESERVED]*4,
: 711      1696 5      ACE_POINTER[ACESL_KEY] + .ACE_POINTER[ACESV_RESERVED]*4);
: 712      1697 5
: 713      1698 5      [ACESC_AUDIT,
: 714      1699 5      ACESC_ALARM]:
: 715      1700 5      ..ACE EQL ..ACE_POINTER
: 716      1701 5      AND CH$EQL (.ACE[ACESB_SIZE] - $BYTEOFFSET (ACEST_AUDITNAME),
: 717      1702 5      ACE[ACEST_AUDITNAME],
: 718      1703 5      .ACE[ACESB_SIZE] - $BYTEOFFSET (ACEST_AUDITNAME),
: 719      1704 5      ACE_POINTER[ACEST_AUDITNAME]);
: 720      1705 5
: 721      1706 5      TES
: 722      1707 5      END
: 723      1708 4      THEN
: 724      1709 5      BEGIN
: 725      1710 5      .ACL_CONTEXT = .ACE_NUMBER;
: 726      1711 5      ACL_CONTEXT[CONTEXT_TYPE] = .ACE_POINTER[ACESB_TYPE];
: 727      1712 5      RETURN 1;
: 728      1713 4      END;
: 729      1714 4
: 730      1715 4      ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACESB_SIZE];
: 731      1716 3      END;
: 732      1717 3      END
: 733      1718 2      UNTIL .ACL_POINTER[ACL$FLINK] EQL ACL_QUEUE_HEAD[ACL$FLINK];
: 734      1719 2      .ACL_CONTEXT = 0;
: 735      1720 2
: 736      1721 2      ! At this point the desired ACE has not been found. Return failure.
: 737      1722 2
: 738      1723 2      IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$NOENTRY);
: 739      1724 2
: 740      1725 1      END;

```

! End of routine ACL_FINDENTRY

				01FC 00000	.ENTRY	ACL_FINDENTRY, Save R2,R3,R4,R5,R6,R7,R8	: 1578
		04	0C	AC D1 00002	CMPL	COUNT, #4	: 1632
				04 1E 00006	BGEQU	1\$:
		50		14 D0 00008	MOVL	#20, R0	: 1633
				04 0000B	RET		:
OC	AC	10	BC	08 00 ED 0000C 1\$:	CMPZV	#0, #8, @ACE, COUNT	: 1638
				18 1B 00013	BLEQU	2\$:
OC	AC		00	6E 00 2C 00015	MOVCS	#0, (SP), #0, COUNT, @ACE	: 1639
				10 BC 0001B			:
		50	10	AC D0 0001D	MOVL	ACE, R0	:
02	A0	21E4	8F	B0 00021	MOVW	#8676, 2(R0)	:
	50	21E4	8F	3C 00027	MOVZWL	#8676, R0	:
				04 0002C	RET		:
04	AC	04	BC	D1 0002D 2\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	: 1643
				22 12 00032	BNEQ	4\$:
		08	BC	D4 00034	CLRL	@ACL_CONTEXT	: 1646
	03	14	AC	E9 00037	BLBC	INTERNAL, 3\$: 1647

OC	AC	00	6E	00EC	31	0003B	BRW	17\$:	
				00	2C	0003E	MOVCS	#0, (SP), #0, COUNT, @ACE	:	
				10	BC	00044			:	
			50	10	AC	D0	MOVL	ACE, R0	:	
		02	A0	09D0	8F	B0	MOVW	#2512, 2(R0)	:	
			50	09D0	8F	3C	MOVZWL	#2512, R0	:	
					04	00055	RET		:	
				58	D4	00056	CLRL	ACE_NUMBER	:	1652
			55	04	AC	D0	MOVL	ACL_QUEUE_HEAD, ACL_POINTER	:	1653
			55		65	D0	MOVL	(ACL_POINTER), ACL_POINTER	:	1656
			54	0C	A5	9E	MOVAB	12(R5), ACE_POINTER	:	1657
			50	08	A5	3C	MOVZWL	8(ACL_POINTER), R0	:	1658
			50		55	C0	ADDL2	ACL_POINTER, R0	:	
			50		54	D1	CMPL	ACE_POINTER, R0	:	
				03	1F	0006D	BLSSU	7\$:	
				00A8	31	0006F	BRW	15\$:	
			56		58	D6	INCL	ACE_NUMBER	:	1661
			01	10	AC	D0	MOVL	ACE, R6	:	1669
0020		08		01	A6	8F	CASEB	1(R6), #1, #8	:	
0020		0020		0027		0007D	.WORD	11\$-8\$,-	:	
		0012		0072		00085		10\$-8\$,-	:	
				0020		0008D		10\$-8\$,-	:	
								10\$-8\$,-	:	
								10\$-8\$,-	:	
								12\$-8\$,-	:	
								12\$-8\$,-	:	
								9\$-8\$,-	:	
								10\$-8\$,-	:	
								10\$-8\$:	
			51		66	9A	MOVZBL	(R6), R1	:	1682
			50		64	9A	MOVZBL	(ACE_POINTER), R0	:	1683
50		00	66		51	2D	CMPC5	R1, (R6), #0, R0, (ACE_POINTER)	:	1682
					64				:	
					63	11	BRB	13\$:	
				01	A6	91	CMPB	1(R6), 1(ACE_POINTER)	:	1677
					5C	11	BRB	13\$:	
			51		8F	CB	BICL3	#983040, (R6), R1	:	1686
			50		8F	CB	BICL3	#983040, (ACE_POINTER), R0	:	1689
					51	D1	CMPL	R1, R0	:	
					58	12	BNEQ	14\$:	
			52		66	9A	MOVZBL	(R6), R2	:	1691
			04		00	EF	EXTZV	#0, #4, 2(R6), R1	:	1692
			51		02	78	ASHL	#2, R1, R0	:	
			52		50	C2	SUBL2	R0, R2	:	
			52		08	C2	SUBL2	#8, R2	:	
			53		64	9A	MOVZBL	(ACE_POINTER), R3	:	1694
			04		00	EF	EXTZV	#0, #4, 2(ACE_POINTER), R0	:	1695
50		02	A4		02	78	ASHL	#2, R0, R7	:	
			57		57	C2	SUBL2	R7, R3	:	
					08	C2	SUBL2	#8, R3	:	
				08	A440	DF	PUSHAL	8(ACE_POINTER)[R0]	:	1691
				08	A641	DF	PUSHAL	8(R6)[R1]	:	
					52	2D	CMPC5	R2, @ (SP)+, #0, R3, @ (SP)+	:	
					9E				:	
					11	11	BRB	13\$:	
			64		66	D1	CMPL	(R6), (ACE_POINTER)	:	1700
					1D	12	BNEQ	14\$:	
			50		66	9A	MOVZBL	(R6), R0	:	1701

ACLSUBR
V04-000

ACL_FINDENTRY - locate a specific ACE

M 14
15-Sep-1984 23:51:08
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[F11X.SRC]ACLSUBR.B32;1
Page 23
(6)

08	BC	08	A4	08	50	08	C2	000F7	SUBL2	#8, R0	:	
					A6		50	29	CMPC3	R0, 8(R6), 8(ACE_POINTER)	:	1704
							0F	12	BNEQ	14\$:	
					BC		58	D0	MOVL	ACE_NUMBER, @ACL_CONTEXT	:	1710
					18		A4	F0	INSV	1(ACE_POINTER), #24, #8, @ACL_CONTEXT	:	1711
					50		01	D0	MOVL	#1, R0	:	1712
								04	RET		:	
								64	MOVZBL	(ACE_POINTER), R0	:	1715
					54		50	C0	ADDL2	R0, ACE_POINTER	:	
							FF49	31	BRW	6\$:	1658
							65	D1	CMPL	(ACL_POINTER), ACL_QUEUE_HEAD	:	1718
					AC		03	13	BEQL	16\$:	
							FF39	31	BRW	5\$:	
							08	BC	CLRL	@ACL_CONTEXT	:	1719
							14	AC	BLBC	INTERNAL, 18\$:	1723
							50	D4	CLRL	R0	:	
								04	RET		:	
					6E		00	2C	MOVCS	#0, (SP), #0, COUNT, @ACE	:	
							10	BC			:	
					50		10	AC	MOVL	ACE, R0	:	
							09D8	8F	MOVW	#2520, 2(R0)	:	
					50		09D8	8F	MOVZWL	#2520, R0	:	
							04	00144	RET		:	1725

; Routine Size: 325 bytes, Routine Base: \$CODE\$ + 046E

```

742 1726 1 %SBTTL 'ACL_FINDTYPE - locate a specific type of ACE'
743 1727 1 GLOBAL ROUTINE ACL_FINDTYPE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL) =
744 1728 1
745 1729 1 ++
746 1730 1
747 1731 1 FUNCTIONAL DESCRIPTION:
748 1732 1
749 1733 1     This routine locates an Access Control Entry of a specific type.
750 1734 1     The ACL context is set accordingly.
751 1735 1
752 1736 1 CALLING SEQUENCE:
753 1737 1     ACL_FINDTYPE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL)
754 1738 1
755 1739 1 INPUT PARAMETERS:
756 1740 1     ACL_QUEUE_HEAD: address of queue header for ACL
757 1741 1     ACL_CONTEXT: address of ACL context longword
758 1742 1     COUNT: size of the user Access Control Entry
759 1743 1     ACE: address of the user Access Control Entry
760 1744 1     INTERNAL: 0 call generated by a user request
761 1745 1               1 call generated within the system
762 1746 1
763 1747 1 IMPLICIT INPUTS:
764 1748 1     NONE
765 1749 1
766 1750 1 OUTPUT PARAMETERS:
767 1751 1     NONE
768 1752 1
769 1753 1 IMPLICIT OUTPUTS:
770 1754 1     NONE
771 1755 1
772 1756 1 ROUTINE VALUE:
773 1757 1     1 if successful
774 1758 1     0 otherwise
775 1759 1
776 1760 1 SIDE EFFECTS:
777 1761 1     NONE
778 1762 1
779 1763 1 --
780 1764 1
781 1765 2 BEGIN
782 1766 2
783 1767 2 MAP
784 1768 2     ACL_QUEUE_HEAD : REF $BBLOCK,      ! Queue header for ACL
785 1769 2     ACL_CONTEXT  : REF $BBLOCK,      ! Context longword
786 1770 2     ACE         : REF $BBLOCK;       ! Address of the user ACE
787 1771 2
788 1772 2 LOCAL
789 1773 2     ACL_POINTER   : REF $BBLOCK,      ! Pointer to current ACL segment
790 1774 2     ACL_SPLIT    : REF $BBLOCK,      ! Offset to current ACE
791 1775 2     ACE_POINTER  : REF $BBLOCK,      ! Pointer to current ACE
792 1776 2     ACE_NUMBER;   ! Index of ACE in ACL
793 1777 2
794 1778 2
795 1779 2 ! Sanity check the length of the supplied ACE.
796 1780 2
797 1781 2 IF .COUNT LSSU 4
798 1782 2 THEN RETURN $$$_BADPARAM;
```



```
799 1783 2
800 1784 2 ! Determine if the ACL is empty. If it is, set the context to zero, indicate
801 1785 2 ! a failure by clearing the returning ACE, and return success.
802 1786 2
803 1787 2 IF .ACL_QUEUE_HEAD[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
804 1788 2 THEN
805 1789 2 BEGIN
806 1790 2 .ACL_CONTEXT = 0;
807 1791 2 IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$_ACLEMPY);
808 1792 2 END;
809 1793 2
810 1794 2 ! If the search is for an ACE type different from the last ACE type found,
811 1795 2 ! start from the beginning of the ACL. Otherwise, continue the search from
812 1796 2 ! the ACE after the last one found. If the ACE type is found, save the
813 1797 2 ! current context and return the contents of the ACE. If the ACE type was
814 1798 2 ! not found, determine whether or not it is the first time through and set
815 1799 2 ! the appropriate error status.
816 1800 2
817 1801 2 IF .ACL_CONTEXT[CONTEXT_TYPE] EQL 0
818 1802 2 OR .ACL_CONTEXT[CONTEXT_TYPE] NEQ .ACE[ACESB_TYPE]
819 1803 2 THEN .ACL_CONTEXT = 0;
820 1804 2 ACE_NUMBER = ACL LocateACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX] + 1, ACL_POINTER, ACL_SPLIT);
821 1805 2 ACE_POINTER = ACE_POINTER[ACL$$_LIST] + .ACL_SPLIT;
822 1806 2
823 1807 2 WHILE 1
824 1808 2 DO
825 1809 2 BEGIN
826 1810 2 IF .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$$_SIZE]
827 1811 2 THEN
828 1812 2 BEGIN
829 1813 2 ACE_POINTER = .ACL_POINTER[ACL$$_FLINK];
830 1814 2 ACE_POINTER = ACE_POINTER[ACL$$_LIST];
831 1815 2 END;
832 1816 2 IF ACE_POINTER[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
833 1817 2 THEN EXITLOOP;
834 1818 2
835 1819 2 IF .ACE[ACESB_TYPE] EQL .ACE_POINTER[ACESB_TYPE]
836 1820 2 AND (IF .ACE[ACESB_TYPE] NEQ ACES$_INFO
837 1821 2 THEN 1
838 1822 2 ELSE .ACE[ACESV_INFO_TYPE] EQL .ACE_POINTER[ACESV_INFO_TYPE])
839 1823 2 THEN
840 1824 2 BEGIN
841 1825 2 .ACL_CONTEXT = .ACE_NUMBER;
842 1826 2 ACL_CONTEXT[CONTEXT_TYPE] = .ACE_POINTER[ACESB_TYPE];
843 1827 2 CH$COPY (.ACE_POINTER[ACESB_SIZE], .ACE_POINTER,
844 1828 2 0, .COUNT, .ACE);
845 1829 2 RETURN 1;
846 1830 2 END;
847 1831 2
848 1832 2 ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACESB_SIZE];
849 1833 2 ACE_NUMBER = .ACE_NUMBER + 1;
850 1834 2 END;
851 1835 2
852 1836 2 ! At this point the end of the ACL has been reached. Return failure.
853 1837 2
854 1838 2 .ACL_CONTEXT = 0;
855 1839 2 IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$_NOENTRY);
```


: 856
: 8571840 2
1841 1 END;

! End of routine ACL_FINDTYPE

				00FC 00000	.ENTRY	ACL_FINDTYPE, Save R2,R3,R4,R5,R6,R7	1727
	5E		08	C2 00002	SUBL2	#8, SP	
	04	0C	AC	D1 00005	CMPL	COUNT, #4	1781
			04	1E 00009	BGEQU	1\$	
	50		14	D0 0000B	MOVL	#20, R0	1782
				04 0000E	RET		
04	AC	04	BC	D1 0000F 1\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	1787
			22	12 00014	BNEQ	3\$	
	03		08	BC D4 00016	CLRL	@ACL_CONTEXT	1790
			14	AC E9 00019	BLBC	INTERNAL, 2\$	1791
				00BA 31 0001D	BRW	11\$	
0C	AC		00	00 2C 00020 2\$:	MOVCS	#0, (SP), #0, COUNT, @ACE	
			10	BC 00026			
	50		10	AC D0 00028	MOVL	ACE, R0	
	02	A0	09D0	8F B0 0002C	MOVW	#2512, 2(R0)	
		50	09D0	8F 3C 00032	MOVZWL	#2512, R0	
				04 00037	RET		
00	08	BC	08	18 ED 00038 3\$:	CMPZV	#24, #8, @ACL_CONTEXT, #0	1801
				10 13 0003E	BEQL	4\$	
	50		10	AC D0 00040	MOVL	ACE, R0	1802
	51		01	A0 9A 00044	MOVZBL	1(R0), R1	
51	08	BC	08	18 ED 00048	CMPZV	#24, #8, @ACL_CONTEXT, R1	
				03 13 0004E	BEQL	5\$	
			08	BC D4 00050 4\$:	CLRL	@ACL_CONTEXT	1803
				5E DD 00053 5\$:	PUSHL	SP	1804
			08	AE 9F 00055	PUSHAB	ACL_POINTER	
7E	08	BC	18	00 EF 00058	EXTZV	#0, #24, @ACL_CONTEXT, -(SP)	
				6E D6 0005E	INCL	(SP)	
			04	AC DD 00060	PUSHL	ACL_QUEUE_HEAD	
	0000V	CF	04	FB 00063	CALLS	#4, ACL_LOCATEACE	
		57	50	D0 00068	MOVL	R0, ACE_NUMBER	
	56	04	6E	C1 0006B	ADDL3	ACL_SPLIT, ACL_POINTER, R6	1805
			0C	C0 00070	ADDL2	#12, ACE_POINTER	
			04	AE D0 00073 6\$:	MOVL	ACL_POINTER, R0	1810
			08	A0 3C 00077	MOVZWL	8(R0), R1	
				50 C0 0007B	ADDL2	R0, R1	
				56 D1 0007E	CMPL	ACE_POINTER, R1	
			09	1F 00081	BLSSU	7\$	
	04	AE	60	D0 00083	MOVL	(R0), ACL_POINTER	1813
	56	04	0C	C1 00087	ADDL3	#12, ACL_POINTER, ACE_POINTER	1814
		04	AE	D1 0008C 7\$:	CMPL	ACL_POINTER, ACL_QUEUE_HEAD	1816
			40	13 00091	BEQL	10\$	
			10	AC D0 00093	MOVL	ACE, R0	1819
	01	A6	01	A0 91 00097	CMPB	1(R0), 1(ACE_POINTER)	
				2B 12 0009C	BNEQ	9\$	
	07		01	A0 91 0009E	CMPB	1(R0), #7	1820
				0B 12 000A2	BNEQ	8\$	
51	02	A6	02	A0 8D 000A4	XORB3	2(R0), 2(ACE_POINTER), R1	1822
		0F		51 93 000AA	BITB	R1, #15	
				1A 12 000AD	BNEQ	9\$	

ACLSUBR
V04-000

ACL_FINDTYPE - locate a specific type of ACE

D 15
15-Sep-1984 23:51:08
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[F11X.SRC]ACLSUBR.B32;1 Page 27
(7)

08	BC	08	08	BC	57	D0	000AF	8\$:	MOVL	ACE_NUMBER, @ACL_CONTEXT	:	1825	
				18	01	A6	F0	000B3	INSV	1(ACE_POINTER), #24, #8, @ACL_CONTEXT	:	1826	
0C	AC	00		50		66	9A	000BA	MOVZBL	(ACE_POINTER), R0	:	1827	
				66	10	50	2C	000BD	MOVCS	R0, (ACE_POINTER), #0, COUNT, @ACE	:	1828	
						BC		000C3			:		
				50		01	D0	000C5	MOVL	#1, R0	:	1829	
							04	000C8	RET		:		
				50		66	9A	000C9	MOVZBL	(ACE_POINTER), R0	:	1832	
				56		50	C0	000CC	ADDL2	R0, ACE_POINTER	:		
						57	D6	000CF	INCL	ACE_NUMBER	:	1833	
						A0	11	000D1	BRB	6\$:	1807	
			03		08	BC	D4	000D3	CLRL	@ACL_CONTEXT	:	1838	
					14	AC	E9	000D6	BLBC	INTERNAL, 12\$:	1839	
						50	D4	000DA	CLRL	R0	:		
							04	000DC	RET		:		
0C	AC	00		6E		00	2C	000DD	MOVCS	#0, (SP), #0, COUNT, @ACE	:		
					10	BC		000E3			:		
				50		10	AC	D0	000E5	MOVL	ACE, R0	:	
		02		A0	09D8	8F	B0	000E9	MOVW	#2520, 2(R0)	:		
				50	09D8	8F	3C	000EF	MOVZWL	#2520, R0	:		
						04	000F4		RET		:	1841	

; Routine Size: 245 bytes, Routine Base: \$CODE\$ + 05B3

ACL_DELETEACL - remove entire ACL from object

```

859 1842 1 %SBTTL 'ACL DELETEACL - remove entire ACL from object'
860 1843 1 GLOBAL ROUTINE ACL_DELETEACL (ACL_QUEUE_HEAD, ACL_CONTEXT) =
861 1844 1
862 1845 1 ++
863 1846 1
864 1847 1 FUNCTIONAL DESCRIPTION:
865 1848 1
866 1849 1 This routine removes all the Access Control Entries from a file,
867 1850 1 except the ACE that granted the calling user access to the file
868 1851 1 and any protected ACEs.
869 1852 1
870 1853 1 CALLING SEQUENCE:
871 1854 1 ACL_DELETEACL (ACL_QUEUE_HEAD, ACL_CONTEXT)
872 1855 1
873 1856 1 INPUT PARAMETERS:
874 1857 1 ACL_QUEUE_HEAD: address of queue header for ACL
875 1858 1 ACL_CONTEXT: address of ACL context longword
876 1859 1 Note: A context of zero means an internal call,
877 1860 1 meaning that protected ACEs are also deleted.
878 1861 1
879 1862 1 IMPLICIT INPUTS:
880 1863 1 NONE
881 1864 1
882 1865 1 OUTPUT PARAMETERS:
883 1866 1 NONE
884 1867 1
885 1868 1 IMPLICIT OUTPUTS:
886 1869 1 NONE
887 1870 1
888 1871 1 ROUTINE VALUE:
889 1872 1 1
890 1873 1
891 1874 1 SIDE EFFECTS:
892 1875 1 All of the ACE's for a file, except for that ACE that granted access
893 1876 1 to the file and protected ACEs, are removed. This may or may not be
894 1877 1 all ACE's depending on whether or not the caller is the file owner.
895 1878 1 The file header and all extension headers are modified to reflect the
896 1879 1 new ACL.
897 1880 1
898 1881 1 --
899 1882 1
900 1883 2 BEGIN
901 1884 2
902 1885 2 MAP
903 1886 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
904 1887 2 ACL_CONTEXT : REF $BBLOCK; ! Context longword
905 1888 2
906 1889 2 LOCAL
907 1890 2 ACL_SEGMENT : REF $BBLOCK, ! Address of current segment
908 1891 2 NEW_SEGMENT : REF $BBLOCK, ! Address of new ACL segment
909 1892 2 OLD_SEGMENT : REF $BBLOCK, ! Address of old ACL segment
910 1893 2 NEW_POINTER : REF $BBLOCK, ! Where to put the new ACE
911 1894 2 OLD_POINTER : REF $BBLOCK, ! Where to get the old ACE
912 1895 2 NEW_LENGTH, ! Length of new ACL segment
913 1896 2 ACE_LENGTH, ! Length of protected ACE
914 1897 2 DUMMY; ! Throw-away from REMQUE
915 1898 2
```



```

: 916 1899 2 ! Loop through removing each ACL segment and deallocate the memory. At this
: 917 1900 2 ! time, no check is made to see if any ACE within the ACL segment grants
: 918 1901 2 ! access to the file by the caller.
: 919 1902 2
: 920 1903 2 ACL_SEGMENT = .ACL_QUEUE_HEAD[ACL$$_FLINK];
: 921 1904 2 UNTIL .ACL_SEGMENT EQ .ACL_QUEUE_HEAD[ACL$$_FLINK]
: 922 1905 2 DO
: 923 1906 2 BEGIN
: 924 1907 2 OLD_SEGMENT = .ACL_SEGMENT;
: 925 1908 2 ACL_SEGMENT = .ACL_SEGMENT[ACL$$_FLINK];
: 926 1909 2 REMQUE (.OLD_SEGMENT, DUMMY);
: 927 1910 2
: 928 1911 2 ! Preserve the protected ACEs if necessary.
: 929 1912 2
: 930 1913 2 IF .ACL_CONTEXT NEQ 0
: 931 1914 2 THEN
: 932 1915 2 BEGIN
: 933 1916 2 NEW_POINTER = OLD_POINTER = OLD_SEGMENT[ACL$$_LIST];
: 934 1917 2 NEW_LENGTH = 0;
: 935 1918 2 UNTIL .OLD_POINTER GEQ .OLD_SEGMENT + .OLD_SEGMENT[ACL$$_SIZE]
: 936 1919 2 DO
: 937 1920 2 BEGIN
: 938 1921 2 ACE_LENGTH = .OLD_POINTER[ACE$$_SIZE];
: 939 1922 2 IF .OLD_POINTER[ACE$$_PROTECTED]
: 940 1923 2 THEN
: 941 1924 2 BEGIN
: 942 1925 2 CH$MOVE (.ACE_LENGTH, .OLD_POINTER, .NEW_POINTER);
: 943 1926 2 NEW_LENGTH = .NEW_LENGTH + .ACE_LENGTH;
: 944 1927 2 NEW_POINTER = .NEW_POINTER + .ACE_LENGTH;
: 945 1928 2 END;
: 946 1929 2 OLD_POINTER = .OLD_POINTER + .ACE_LENGTH;
: 947 1930 2 END;
: 948 1931 2 IF .NEW_LENGTH NEQ 0
: 949 1932 2 THEN
: 950 1933 2 BEGIN
: 951 1934 2 NEW_SEGMENT = ALLOC_PAGED (ACL$$_LENGTH + .NEW_LENGTH, ACL_TYPE);
: 952 1935 2 NEW_SEGMENT[ACL$$_SIZE] = ACL$$_LENGTH + .NEW_LENGTH;
: 953 1936 2 CH$MOVE (.NEW_LENGTH, OLD_SEGMENT[ACL$$_LIST], NEW_SEGMENT[ACL$$_LIST]);
: 954 1937 2 INSQUE (.NEW_SEGMENT, .ACL_SEGMENT[ACL$$_BLINK]);
: 955 1938 2 END;
: 956 1939 2 END;
: 957 1940 2
: 958 1941 2 DALLOC_PAGED (.OLD_SEGMENT, ACL_TYPE);
: 959 1942 2 END;
: 960 1943 2
: 961 1944 2 ! Set the context to zero, and return success.
: 962 1945 2
: 963 1946 2 IF .ACL_CONTEXT NEQ 0
: 964 1947 2 THEN .ACL_CONTEXT = 0;
: 965 1948 2
: 966 1949 2 RETURN 1;
: 967 1950 2
: 968 1951 1 END;

```

! End of routine ACL_DELETEACL

				OFFC 00000	.ENTRY	ACL_DELETEACL, Save R2,R3,R4,R5,R6,R7,R8,- R9,R10,R11	
			5E	08 C2 00002	SUBL2	#8, SP	1843
			5A	04 BC D0 00005	MOVL	@ACL_QUEUE_HEAD, ACL_SEGMENT	1903
		04	AC	5A D1 00009 1\$:	CMPL	ACL_SEGMENT, ACL_QUEUE_HEAD	1904
			56	6C 13 0000D	BEQL	6\$	
			5A	5A D0 0000F	MOVL	ACL_SEGMENT, OLD_SEGMENT	1907
			6E	6A D0 00012	MOVL	(ACL_SEGMENT), ACL_SEGMENT	1908
				66 0F 00015	REMQUE	(OLD_SEGMENT), DUMMY	1909
				08 AC D5 00018	TSTL	ACL_CONTEXT	1913
			57	51 13 0001B	BEQL	5\$	
		04	AE	0C A6 9E 0001D	MOVAB	12(R6), OLD_POINTER	1916
				57 D0 00021	MOVL	OLD_POINTER, NEW_POINTER	
			50	59 D4 00025	CLRL	NEW_LENGTH	1917
			50	08 A6 3C 00027 2\$:	MOVZWL	8(OLD_SEGMENT), R0	1918
			50	56 C0 0002B	ADDL2	OLD_SEGMENT, R0	
				57 D1 0002E	CMPL	OLD_POINTER, R0	
			5B	19 1E 00031	BGEQU	4\$	
			A7	67 9A 00033	MOVZBL	(OLD_POINTER), ACE_LENGTH	1921
04	OC	03	67	01 E1 00036	BBC	#1, 3(OLD_POINTER), 3\$	1922
	BE		59	5B 28 0003B	MOVCL3	ACE_LENGTH, (OLD_POINTER), @NEW_POINTER	1925
		04	AE	5B C0 00040	ADDL2	ACE_LENGTH, NEW_LENGTH	1926
			57	5B C0 00043	ADDL2	ACE_LENGTH, NEW_POINTER	1927
				5B C0 00047 3\$:	ADDL2	ACE_LENGTH, OLD_POINTER	1929
				DB 11 0004A	BRB	2\$	1918
				59 D5 0004C 4\$:	TSTL	NEW_LENGTH	1931
				1E 13 0004E	BEQL	5\$	
				07 DD 00050	PUSHL	#7	1934
				0C A9 9F 00052	PUSHAB	12(NEW_LENGTH)	
				02 FB 00055	CALLS	#2, ALLOC_PAGED	
			58	50 D0 0005C	MOVL	R0, NEW_SEGMENT	
08	A8		59	0C A1 0005F	ADDW3	#12, NEW_LENGTH, 8(NEW_SEGMENT)	1935
OC	A8	OC	A6	59 28 00064	MOVCL3	NEW_LENGTH, 12(OLD_SEGMENT), - 12(NEW_SEGMENT)	1936
		04	BA	68 0E 0006A	INSQUE	(NEW_SEGMENT), @4(ACL_SEGMENT)	1937
				07 DD 0006E 5\$:	PUSHL	#7	1941
				56 DD 00070	PUSHL	OLD_SEGMENT	
				02 FB 00072	CALLS	#2, DALLOC_PAGED	
				8E 11 00079	BRB	1\$	1904
				08 AC D5 0007B 6\$:	TSTL	ACL_CONTEXT	1946
				03 13 0007E	BEQL	7\$	
			50	08 BC D4 00080	CLRL	@ACL_CONTEXT	1947
				01 D0 00083 7\$:	MOVL	#1, R0	1949
				04 00086	RET		1951

; Routine Size: 135 bytes, Routine Base: \$CODE\$ + 06A8


```

: 970      1952 1 %SBTTL 'ACL_READACL - read one or more ACEs'
: 971      1953 1 GLOBAL ROUTINE ACL_READACL (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER) =
: 972      1954 1
: 973      1955 1 ++
: 974      1956 1
: 975      1957 1 FUNCTIONAL DESCRIPTION:
: 976      1958 1
: 977      1959 1 This routine returns as much of the file ACL as will fit in the user's
: 978      1960 1 buffer. Successive calls will return the unread portions of the ACL
: 979      1961 1 until the entire ACL has been read. If an attempt is made to read
: 980      1962 1 beyond the end of the ACL, a error is returned to indicate that there
: 981      1963 1 is no more to be read.
: 982      1964 1
: 983      1965 1 CALLING SEQUENCE:
: 984      1966 1 ACL_READACL (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER)
: 985      1967 1
: 986      1968 1 INPUT PARAMETERS:
: 987      1969 1 ACL_QUEUE_HEAD: address of queue header for ACL
: 988      1970 1 ACL_CONTEXT: address of ACL context longword
: 989      1971 1 LENGTH: size of the user buffer
: 990      1972 1 ACE_BUFFER: address of the user buffer
: 991      1973 1
: 992      1974 1 IMPLICIT INPUTS:
: 993      1975 1 NONE
: 994      1976 1
: 995      1977 1 OUTPUT PARAMETERS:
: 996      1978 1 NONE
: 997      1979 1
: 998      1980 1 IMPLICIT OUTPUTS:
: 999      1981 1 NONE
1000      1982 1
1001      1983 1 ROUTINE VALUE:
1002      1984 1 1 if successful
1003      1985 1 0 otherwise
1004      1986 1
1005      1987 1 SIDE EFFECTS:
1006      1988 1 The users's buffer is filled with as much of the ACL as will fit.
1007      1989 1 (Only entire ACE's are transferred.) The ACL context is then updated
1008      1990 1 to point to the next available ACE.
1009      1991 1
1010      1992 1 --
1011      1993 1
1012      1994 2 BEGIN
1013      1995 2
1014      1996 2 MAP
1015      1997 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
1016      1998 2 ACL_CONTEXT : REF $BBLOCK; ! Context longword
1017      1999 2
1018      2000 2 LOCAL
1019      2001 2 COUNT, ! Remaining buffer size
1020      2002 2 ACE : REF $BBLOCK, ! Address of the user ACE buffer
1021      2003 2 ACL_POINTER : REF $BBLOCK, ! Pointer to current ACL segment
1022      2004 2 ACL_SPLIT : REF $BBLOCK, ! Offset to current ACE
1023      2005 2 ACE_POINTER : REF $BBLOCK, ! Pointer to current ACE
1024      2006 2 ACE_NUMBER; ! Index of ACE in ACL
: 1025      2007 2
: 1026      2008 2
```



```
: 1027      2009 2 ! Initialize the buffer parameters.
: 1028      2010
: 1029      2011 22 COUNT = .LENGTH;
: 1030      2012 22 ACE = .ACE_BUFFER;
: 1031      2013
: 1032      2014 22 ! Sanity check the length of the supplied ACE.
: 1033      2015
: 1034      2016 22 IF .COUNT LSSU 4
: 1035      2017 22 THEN RETURN SSS_BADPARAM;
: 1036      2018
: 1037      2019 22 ! If the ACL is empty, return an error.
: 1038      2020
: 1039      2021 22 IF .ACL_QUEUE_HEAD[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1040      2022 22 THEN
: 1041      2023 22 BEGIN
: 1042      2024 22 .ACL_CONTEXT = 0;
: 1043      2025 22 ACL_ERROR (SS$_ACLEMPY);
: 1044      2026 22 END;
: 1045      2027
: 1046      2028 22 ! Start reading ACE's from next available. If the ACL context is zero,
: 1047      2029 22 ! start reading ACE's from the beginning of the ACL. In either case only
: 1048      2030 22 ! fill the user's buffer with as many whole ACE's as will fit. Then save
: 1049      2031 22 ! the context for the next time through. An error is given when an attempt
: 1050      2032 22 ! is made to read beyond the end of the ACL.
: 1051      2033
: 1052      2034 22 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX] + 1, ACL_POINTER, ACL_SPLIT);
: 1053      2035 22 ACE_POINTER = ACE_POINTER[ACL$$_LIST] + .ACL_SPLIT;
: 1054      2036
: 1055      2037 22 WHILE 1
: 1056      2038 22 DO
: 1057      2039 22 BEGIN
: 1058      2040 22 IF .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$$_SIZE]
: 1059      2041 22 THEN
: 1060      2042 22 BEGIN
: 1061      2043 22 ACL_POINTER = .ACL_POINTER[ACL$$_FLINK];
: 1062      2044 22 ACE_POINTER = ACL_POINTER[ACL$$_LIST];
: 1063      2045 22 END;
: 1064      2046 22 IF ACL_POINTER[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1065      2047 22 THEN EXITLOOP;
: 1066      2048
: 1067      2049 22 IF .ACE_POINTER[ACESB_SIZE] GTRU .COUNT
: 1068      2050 22 THEN
: 1069      2051 22 BEGIN
: 1070      2052 22 .ACL_CONTEXT = .ACE_NUMBER - 1;
: 1071      2053 22 IF .ACE EQLA .ACE_BUFFER THEN ACL_ERROR (SS$_BUFFEROVF);
: 1072      2054 22 CH$FILL (0, .COUNT, .ACE);
: 1073      2055 22 RETURN 1;
: 1074      2056 22 END;
: 1075      2057 22 CH$MOVE (.ACE_POINTER[ACESB_SIZE], .ACE_POINTER, .ACE);
: 1076      2058 22 ACE = .ACE + .ACE_POINTER[ACESB_SIZE];
: 1077      2059 22 COUNT = .COUNT - .ACE_POINTER[ACESB_SIZE];
: 1078      2060
: 1079      2061 22 ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACESB_SIZE];
: 1080      2062 22 ACE_NUMBER = .ACE_NUMBER + 1;
: 1081      2063 22 END;
: 1082      2064
: 1083      2065 2 ! At this point the end of the ACL has been reached. Return the ACE's
```



```
: 1084      2066 2 ! gathered so far, and set the context to point of the end in case another
: 1085      2067 2 ! context operation takes place. If nothing was returned (i.e., we were
: 1086      2068 2 ! at the end of the ACL to start with, return the status.
: 1087      2069 2
: 1088      2070 2 .ACL_CONTEXT = .ACE_NUMBER;
: 1089      2071 2 IF .ACE_EQLA .ACE_BUFFER
: 1090      2072 2 THEN ACL_ERROR (SS$_NOMOREACE);
: 1091      2073 2
: 1092      2074 2 CH$FILL (0, .COUNT, .ACE);
: 1093      2075 2 RETURN 1;
: 1094      2076 2
: 1095      2077 1 END;
```

! End of routine ACL_READACL

				03FC 00000	.ENTRY	ACL_READACL, Save R2,R3,R4,R5,R6,R7,R8,R9	1953
		5E		08 C2 00002	SUBL2	#8, SP	
		58	0C	AC D0 00005	MOVL	LENGTH, COUNT	2011
		57	10	AC D0 00009	MOVL	ACE_BUFFER, ACE	2012
		04		58 D1 0000D	CMPL	COUNT, #4	2016
				04 1E 00010	BGEQU	1\$	
		50		14 D0 00012	MOVL	#20, R0	2017
				04 00015	RET		
	04	AC	04	BC D1 00016 1\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	2021
				15 12 0001B	BNEQ	2\$	
			08	BC D4 0001D	CLRL	@ACL_CONTEXT	2024
58		00	6E	00 2C 00020	MOVCS	#0, (SP), #0, COUNT, (ACE)	2025
				67 00025			
	02	A7	09D0	8F B0 00026	MOVW	#2512, 2(ACE)	
		50	09D0	8F 3C 0002C	MOVZWL	#2512, R0	
				04 00031	RET		
				5E DD 00032 2\$:	PUSHL	SP	2034
			08	AE 9F 00034	PUSHAB	ACL_POINTER	
7E	08	BC	18	00 EF 00037	EXTZV	#0, #24, @ACL_CONTEXT, -(SP)	
				6E D6 0003D	INCL	(SP)	
			04	AC DD 0003F	PUSHL	ACL_QUEUE_HEAD	
		0000V	CF	04 FB 00042	CALLS	#4, ACL_LOCATEACE	
			59	50 D0 00047	MOVL	R0, ACE_NUMBER	
		56	04	6E C1 0004A	ADDL3	ACL_SPLIT, ACL_POINTER, R6	2035
			56	0C C0 0004F	ADDL2	#12, ACE_POINTER	
			50	04 AE D0 00052 3\$:	MOVL	ACL_POINTER, R0	2040
			51	08 A0 3C 00056	MOVZWL	8(R0), R1	
			51	50 C0 0005A	ADDL2	R0, R1	
			51	56 D1 0005D	CMPL	ACE_POINTER, R1	
				09 1F 00060	BLSSU	4\$	
	04	AE		60 D0 00062	MOVL	(R0), ACL_POINTER	2043
	56	04	AE	0C C1 00066	ADDL3	#12, ACL_POINTER, ACE_POINTER	2044
		04	AC	04 AE D1 0006B 4\$:	CMPL	ACL_POINTER, ACL_QUEUE_HEAD	2046
				41 13 00070	BEQL	6\$	
58		66	08	00 ED 00072	CMPZV	#0, #8, (ACE_POINTER), COUNT	2049
				1D 1B 00077	BLEQU	5\$	
		08	BC	A9 9E 00079	MOVAB	-1(R9), @ACL_CONTEXT	2052
		10	AC	57 D1 0007E	CMPL	ACE, ACE_BUFFER	2053
				4B 12 00082	BNEQ	7\$	
58		00	6E	00 2C 00084	MOVCS	#0, (SP), #0, COUNT, (ACE)	

; Routine Size: 217 bytes, Routine Base: \$CODES + 072F


```

: 1097 2078 1 %SBTTL 'ACL_ACLLENGTH - determine the size of the ACL'
: 1098 2079 1 GLOBAL ROUTINE ACL_ACLLENGTH (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, LENGTH) =
: 1099 2080 1
: 1100 2081 1 ++
: 1101 2082 1
: 1102 2083 1 FUNCTIONAL DESCRIPTION:
: 1103 2084 1
: 1104 2085 1 This routine returns the length of the Access Control List for the
: 1105 2086 1 specified file.
: 1106 2087 1
: 1107 2088 1 CALLING SEQUENCE:
: 1108 2089 1 ACL_ACLLENGTH (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, LENGTH)
: 1109 2090 1
: 1110 2091 1 INPUT PARAMETERS:
: 1111 2092 1 ACL_QUEUE_HEAD: address of queue header for ACL
: 1112 2093 1 ACL_CONTEXT: address of ACL context longword
: 1113 2094 1 COUNT: size of the user Access Control Entry
: 1114 2095 1 ACE: address of the user Access Control Entry
: 1115 2096 1
: 1116 2097 1 IMPLICIT INPUTS:
: 1117 2098 1 NONE
: 1118 2099 1
: 1119 2100 1 OUTPUT PARAMETERS:
: 1120 2101 1 NONE
: 1121 2102 1
: 1122 2103 1 IMPLICIT OUTPUTS:
: 1123 2104 1 NONE
: 1124 2105 1
: 1125 2106 1 ROUTINE VALUE:
: 1126 2107 1 1
: 1127 2108 1
: 1128 2109 1 SIDE EFFECTS:
: 1129 2110 1 The length of the ACL is returned. In addition, the ACL context
: 1130 2111 1 is cleared.
: 1131 2112 1
: 1132 2113 1 --
: 1133 2114 1
: 1134 2115 2 BEGIN
: 1135 2116 2
: 1136 2117 2 MAP
: 1137 2118 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
: 1138 2119 2 ACL_CONTEXT : REF $BBLOCK; ! Context longword
: 1139 2120 2
: 1140 2121 2 LOCAL
: 1141 2122 2 ACL_POINTER : REF $BBLOCK, ! Pointer to the current segment
: 1142 2123 2 ACL_LENGTH; ! Length of the ACL
: 1143 2124 2
: 1144 2125 2 ! Calculate the length of the ACL.
: 1145 2126 2
: 1146 2127 2 ACL_LENGTH = 0;
: 1147 2128 2
: 1148 2129 2 ACL_POINTER = .ACL_QUEUE_HEAD[ACL$FLINK];
: 1149 2130 2 UNTIL .ACL_POINTER=EQLA ACL_QUEUE_HEAD[ACL$FLINK]
: 1150 2131 2 DO
: 1151 2132 3 BEGIN
: 1152 2133 3 ACL_LENGTH = .ACL_LENGTH + .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH;
: 1153 2134 3 ACL_POINTER = .ACL_POINTER[ACL$FLINK];
```

ACLSUBR
V04-000

ACL_ACLLENGTH - determine the size of the ACL

M 15
15-Sep-1984 23:51:08
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[F11X.SRC]ACLSUBR.B32;1 (10)

Page 36

```
: 1154      2135 2      END;
: 1155      2136 2
: 1156      2137 2      ! Return the length of the ACL.
: 1157      2138 2
: 1158      2139 2      CH$COPY (4, ACL_LENGTH, 0, .COUNT, .LENGTH);
: 1159      2140 2      RETURN 1;
: 1160      2141 2
: 1161      2142 1      END;
```

! End of routine ACL_ACLLENGTH

				003C 00000	.ENTRY	ACL_ACLLENGTH, Save R2,R3,R4,R5	: 2079
				7E D4 00002	CLRL	ACL_LENGTH	: 2127
				BC D0 00004	MOVL	@ACL_QUEUE_HEAD, ACL_POINTER	: 2129
	04	51	04	51 D1 00008 1\$:	CML	ACL_POINTER, ACL_QUEUE_HEAD	: 2130
				10 13 0000C	BEQL	2\$: 2133
		50	08	A1 3C 0000E	MOVZWL	8(ACL_POINTER), R0	: 2133
		50		6E C0 00012	ADDL2	ACL_LENGTH, R0	: 2134
		6E	F4	A0 9E 00015	MOVAB	-12(R0), ACL_LENGTH	: 2134
		51		61 D0 00019	MOVL	(ACL_POINTER), ACL_POINTER	: 2130
				EA 11 0001C	BRB	1\$: 2139
OC	AC			04 2C 0001E 2\$:	MOVCS	#4, ACL_LENGTH, #0, COUNT, @LENGTH	: 2140
		6E	10	BC 00024			: 2142
		50		01 D0 00026	MOVL	#1, R0	: 2140
				04 00029	RET		: 2142

; Routine Size: 42 bytes, Routine Base: \$CODE\$ + 0808

ACL_READACE - read a single ACE

```

1163 2143 1 %SBTTL 'ACL_READACE - read a single ACE'
1164 2144 1 GLOBAL ROUTINE ACL_READACE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE) =
1165 2145 1
1166 2146 1 !++
1167 2147 1
1168 2148 1 FUNCTIONAL DESCRIPTION:
1169 2149 1
1170 2150 1 This routine reads a single ACE at a time from the ACL. If the
1171 2151 1 ACE will not fit, the error code $$$_BUFFEROVF is returned as an
1172 2152 1 ACE error.
1173 2153 1
1174 2154 1 CALLING SEQUENCE:
1175 2155 1 ACL_READACE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE)
1176 2156 1
1177 2157 1 INPUT PARAMETERS:
1178 2158 1 ACL_QUEUE_HEAD: address of queue header for ACL
1179 2159 1 ACL_CONTEXT: address of ACL context longword
1180 2160 1 COUNT: size of the user Access Control Entry
1181 2161 1 ACE: address of the user Access Control Entry
1182 2162 1
1183 2163 1 IMPLICIT INPUTS:
1184 2164 1 NONE
1185 2165 1
1186 2166 1 OUTPUT PARAMETERS:
1187 2167 1 NONE
1188 2168 1
1189 2169 1 IMPLICIT OUTPUTS:
1190 2170 1 NONE
1191 2171 1
1192 2172 1 ROUTINE VALUE:
1193 2173 1 1 if successful
1194 2174 1 error code otherwise
1195 2175 1
1196 2176 1 SIDE EFFECTS:
1197 2177 1 The user's buffer is filled with the next ACE if it will fit.
1198 2178 1 Otherwise an error is indicated.
1199 2179 1
1200 2180 1 !--
1201 2181 1
1202 2182 2 BEGIN
1203 2183 2
1204 2184 2 MAP
1205 2185 2 ACL_QUEUE_HEAD : REF $BLOCK, ! Queue header for ACL
1206 2186 2 ACL_CONTEXT : REF $BLOCK, ! Context longword
1207 2187 2 ACE : REF $BLOCK; ! Address of user ACE buffer
1208 2188 2
1209 2189 2 LOCAL
1210 2190 2 ACL_POINTER : REF $BLOCK, ! Pointer to current ACL segment
1211 2191 2 ACL_SPLIT : REF $BLOCK, ! Offset to current ACE
1212 2192 2 ACE_POINTER : REF $BLOCK, ! Pointer to current ACE
1213 2193 2 ACE_NUMBER; ! Index of ACE in ACL
1214 2194 2
1215 2195 2
1216 2196 2 ! Sanity check the length of the supplied ACE.
1217 2197 2
1218 2198 2 IF .COUNT LESS 4
1219 2199 2 THEN RETURN $$$_BADPARAM;
```



```
: 1220      2200 2
: 1221      2201 2 ! Determine if the ACL is empty. If it is, set the context to zero, and
: 1222      2202 2 ! indicate a failure by clearing the returning ACE, and return success.
: 1223      2203 2
: 1224      2204 2 IF .ACL_QUEUE_HEAD[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1225      2205 2 THEN
: 1226      2206 2     BEGIN
: 1227      2207 2     .ACL_CONTEXT = 0;
: 1228      2208 2     ACL_ERROR (SS$_ACLEEMPTY);
: 1229      2209 2     END;
: 1230      2210 2
: 1231      2211 2 ! Transfer the next available ACE to the user's buffer. If the user's
: 1232      2212 2 ! buffer is not large enough to contain the ACE, the context is unchanged,
: 1233      2213 2 ! and an error is indicated.
: 1234      2214 2
: 1235      2215 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX] + 1, ACL_POINTER, ACL_SPLIT);
: 1236      2216 2 IF .ACL_POINTER[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1237      2217 2 AND .ACL_SPLIT EQL .ACL_POINTER[ACL$$_SIZE] - ACL$$_LENGTH
: 1238      2218 2 THEN ACL_ERROR (SS$_NOMOREACE);
: 1239      2219 2 ACE_POINTER = ACL_POINTER[ACL$$_LIST] + .ACL_SPLIT;
: 1240      2220 2
: 1241      2221 2 ! The next available ACE has been located. Make sure there is room for it.
: 1242      2222 2
: 1243      2223 2 IF .ACE_POINTER[ACE$$_SIZE] GTR .COUNT THEN ACL_ERROR (SS$_BUFFEROVF);
: 1244      2224 2
: 1245      2225 2 ! There is room. Move it to the user's buffer.
: 1246      2226 2
: 1247      2227 2 CH$COPY (.ACE_POINTER[ACE$$_SIZE], .ACE_POINTER, 0, .COUNT, .ACE);
: 1248      2228 2 .ACL_CONTEXT = .ACE_NUMBER;
: 1249      2229 2
: 1250      2230 2 RETURN 1;
: 1251      2231 2
: 1252      2232 1 END;
```

! End of routine ACL_READACE

				00FC 00000	.ENTRY	ACL_READACE, Save R2,R3,R4,R5,R6,R7	: 2144
		5E		08 C2 00002	SUBL2	#8, SP	: 2198
		04	0C	AC D1 00005	CMPL	COUNT, #4	: 2199
				04 1E 00009	BGEQU	1\$: 2204
		50		14 D0 0000B	MOVL	#20, R0	: 2207
				04 0000E	RET		: 2208
	04	AC	04	BC D1 0000F 1\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	
				1B 12 00014	BNEQ	2\$	
			08	BC D4 00016	CLRL	@ACL_CONTEXT	
0C	AC			00 2C 00019	MOVCS	#0, TSP), #0, COUNT, @ACE	
		6E		BC 0001F			
			10	AC D0 00021	MOVL	ACE, R0	
	02	50	10	8F B0 00025	MOVW	#2512, 2(R0)	
		A0	09D0	8F 3C 0002B	MOVZWL	#2512, R0	
		50	09D0	04 00030	RET		
				5E DD 00031 2\$:	PUSHL	SP	: 2215
			08	AE 9F 00033	PUSHAB	ACL_POINTER	
7E				00 EF 00036	EXTZV	#0, #24, @ACL_CONTEXT, -(SP)	
				6E D6 0003C	INCL	(SP)	

			0000V	CF	04	AC	DD	0003E	PUSHL	ACL_QUEUE_HEAD	:
				57		04	FB	00041	CALLS	#4, ACL_LOCATEACE	:
				50	04	50	D0	00046	MOVL	R0, ACE_NUMBER	:
			04	AC		60	D1	00049	MOVL	ACL_POINTER, R0	2216
						24	12	00051	CMPL	(R0), ACL_QUEUE_HEAD	:
				50	08	AO	3C	00053	BNEQ	3\$:
				50		0C	C2	00057	MOVZWL	8(R0), R0	2217
				50		6E	D1	0005A	SUBL2	#12, R0	:
						18	12	0005D	CMPL	ACL_SPLIT, R0	:
OC	AC	00		6E		00	2C	0005F	BNEQ	3\$:
					10	BC		00065	MOVCS	#0, (SP), #0, COUNT, @ACE	2218
				50	10	AC	D0	00067			:
		02		AO	09E0	8F	B0	0006B	MOVL	ACE, R0	:
				50	09E0	8F	3C	00071	MOVW	#2528, 2(R0)	:
							04	00076	MOVZWL	#2528, R0	:
		56	04	AE		6E	C1	00077	RET		:
				56		0C	C0	0007C	ADDL3	ACL_SPLIT, ACL_POINTER, R6	2219
OC	AC	66		08		00	ED	0007F	ADDL2	#12, ACE_POINTER	:
						18	15	00085	CMPZV	#0, #8, (ACE_POINTER), COUNT	2223
OC	AC	00		6E		00	2C	00087	BLEQ	4\$:
					10	BC		0008D	MOVCS	#0, (SP), #0, COUNT, @ACE	:
				50	10	AC	D0	0008F			:
		02		AO	0601	8F	B0	00093	MOVL	ACE, R0	:
				50	0601	8F	3C	00099	MOVW	#1537, 2(R0)	:
							04	0009E	MOVZWL	#1537, R0	:
				50		66	9A	0009F	RET		:
OC	AC	00		66		50	2C	000A2	MOVZBL	(ACE_POINTER), R0	2227
					10	BC		000A8	MOVCS	R0, (ACE_POINTER), #0, COUNT, @ACE	:
		08		BC		57	D0	000AA			:
				50		01	D0	000AE	MOVL	ACE_NUMBER, @ACL_CONTEXT	2228
						04	000B1		MOVL	#1, R0	2230
									RET		2232

; Routine Size: 178 bytes, Routine Base: \$CODE\$ + 0832


```
1254 2233 1 %SBTTL 'ACL_LOCATEACE - locate ACE by context value'
1255 2234 1 GLOBAL ROUTINE ACL_LOCATEACE (ACL_QUEUE_HEAD, ACE_INDEX, ACL_POINTER, ACL_SPLIT) =
1256 2235 1
1257 2236 1 ++
1258 2237 1
1259 2238 1 FUNCTIONAL DESCRIPTION:
1260 2239 1
1261 2240 1 This routine is used to position to a particular Access Control Entry.
1262 2241 1 This is done by the context specified. A context of zero results in
1263 2242 1 positioning to the start of the ACL; a number larger than the ACL
1264 2243 1 size results in positioning to the end.
1265 2244 1
1266 2245 1 CALLING SEQUENCE:
1267 2246 1 ACL_LOCATEACE (ACL_QUEUE_HEAD, ACE_INDEX, ACL_POINTER, ACL_SPLIT)
1268 2247 1
1269 2248 1 INPUT PARAMETERS:
1270 2249 1 ACL_QUEUE_HEAD: address of queue header for ACL
1271 2250 1 ACE_INDEX: index number of ACE to locate
1272 2251 1
1273 2252 1 IMPLICIT INPUTS:
1274 2253 1 NONE
1275 2254 1
1276 2255 1 OUTPUT PARAMETERS:
1277 2256 1 ACL_POINTER: address to store pointer to the selected ACL segment
1278 2257 1 ACL_SPLIT: address to store the offset to the selected ACE
1279 2258 1
1280 2259 1 IMPLICIT OUTPUTS:
1281 2260 1 NONE
1282 2261 1
1283 2262 1 ROUTINE VALUE:
1284 2263 1 0 if the context is invalid (points off the end of the ACL)
1285 2264 1 the numeric position of the ACE
1286 2265 1
1287 2266 1 SIDE EFFECTS:
1288 2267 1 NONE
1289 2268 1
1290 2269 1 --
1291 2270 1
1292 2271 2 BEGIN
1293 2272 2
1294 2273 2 MAP
1295 2274 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
1296 2275 2 ACL_POINTER : REF $BBLOCK; ! Address of the current segment
1297 2276 2
1298 2277 2 LOCAL
1299 2278 2 ACL_SEGMENT : REF $BBLOCK, ! Address of the current segment
1300 2279 2 ACE_POINTER : REF $BBLOCK, ! Pointer to ACE within segment
1301 2280 2 ACE_NUMBER; ! Position of ACE
1302 2281 2
1303 2282 2 ! Locate the ACE by context. IF an append is being done, locate to the
1304 2283 2 ! end of the ACL chain.
1305 2284 2
1306 2285 2 ACE_NUMBER = 0;
1307 2286 2 ACL_SEGMENT = ACL_QUEUE_HEAD[ACL$FLINK];
1308 2287 2 UNTIL .ACL_SEGMENT[ACL$FLINK] EQ ACL_QUEUE_HEAD[ACL$FLINK]
1309 2288 2 DO
1310 2289 5 BEGIN
```



```
: 1311      2290      3      ACL_SEGMENT = .ACL_SEGMENT[ACL$FLINK];
: 1312      2291      3      ACE_POINTER = ACL_SEGMENT[ACL$L_LIST];
: 1313      2292      3      UNTIL .ACE_POINTER GEQA .ACL_SEGMENT + .ACL_SEGMENT[ACL$W_SIZE]
: 1314      2293      3      DO
: 1315      2294      4      BEGIN
: 1316      2295      4      ACE_NUMBER = .ACE_NUMBER + 1;
: 1317      2296      4      IF .ACE_INDEX LEQO .ACE_NUMBER
: 1318      2297      4      THEN
: 1319      2298      5      BEGIN
: 1320      2299      5      .ACL_SPLIT = .ACE_POINTER - ACL_SEGMENT[ACL$L_LIST];
: 1321      2300      5      .ACL_POINTER = .ACL_SEGMENT;
: 1322      2301      5      RETURN .ACE_NUMBER;
: 1323      2302      4      END;
: 1324      2303      4      ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACE$B_SIZE];
: 1325      2304      3      END;
: 1326      2305      2      END;
: 1327      2306      2
: 1328      2307      2      ! The ACE pointed to by the ACL context field does not exist. Set up to
: 1329      2308      2      ! append the ACE to the end of the ACL.
: 1330      2309      2
: 1331      2310      2      .ACL_SPLIT = .ACL_SEGMENT[ACL$W_SIZE] - ACL$C_LENGTH;
: 1332      2311      2      .ACL_POINTER = .ACL_SEGMENT;
: 1333      2312      2      RETURN .ACE_NUMBER + 1;
: 1334      2313      2
: 1335      2314      1      END;

! End of routine ACL_LOCATEACE
```

			000C 00000	.ENTRY	ACL_LOCATEACE, Save R2,R3	: 2234
			51 D4 00002	CLRL	ACE_NUMBER	: 2285
	04	50	04 AC D0 00004	MOVL	ACL_QUEUE_HEAD, ACL_SEGMENT	: 2286
		AC	60 D1 00008 1\$:	CMPL	(ACL_SEGMENT), ACL_QUEUE_HEAD	: 2287
			32 13 0000C	BEQL	4\$: 2290
		50	60 D0 0000E	MOVL	(ACL_SEGMENT), ACL_SEGMENT	: 2291
		52	0C A0 9E 00011	MOVAB	12(R0), ACE_POINTER	: 2292
		53	08 A0 3C 00015 2\$:	MOVZWL	8(ACL_SEGMENT), R3	: 2295
		53	50 C0 00019	ADDL2	ACL_SEGMENT, R3	: 2296
		53	52 D1 0001C	CMPL	ACE_POINTER, R3	: 2299
			E7 1E 0001F	BGEQU	1\$: 2300
		51	51 D6 00021	INCL	ACE_NUMBER	: 2301
			AC D1 00023	CMPL	ACE_INDEX, ACE_NUMBER	: 2303
			0F 1A 00027	BGTRU	3\$: 2292
53		52	50 C3 00029	SUBL3	ACL_SEGMENT, ACE_POINTER, R3	: 2310
	10	BC	A3 9E 0002D	MOVAB	-12(R3), @ACL_SPLIT	: 2311
	0C	BC	50 D0 00032	MOVL	ACL_SEGMENT, @ACL_POINTER	: 2312
			17 11 00036	BRB	5\$: 2314
		53	62 9A 00038 3\$:	MOVZBL	(ACE_POINTER), R3	: 2292
		52	53 C0 0003B	ADDL2	R3, ACE_POINTER	: 2299
			D5 11 0003E	BRB	2\$: 2300
	10	BC	08 A0 3C 00040 4\$:	MOVZWL	8(ACL_SEGMENT), @ACL_SPLIT	: 2301
	10	BC	0C C2 00045	SUBL2	#12, @ACL_SPLIT	: 2303
	0C	BC	50 D0 00049	MOVL	ACL_SEGMENT, @ACL_POINTER	: 2311
		50	51 D6 0004D	INCL	R1	: 2312
			51 D0 0004F 5\$:	MOVL	R1, R0	: 2314
			04 00052	RET		: 2314

ACLSUBR
V04-000

ACL_LOCATEACE - locate ACE by context value

F 16
15-Sep-1984 23:51:08
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742
DISK\$VM\$MASTER:[F11X.SRC]ACLSUBR.B32;1 (12) Page 42

; Routine Size: 83 bytes, Routine Base: \$CODE\$ + 08E4

; 1336 2315 1
; 1337 2316 1 END
; 1338 2317 0 ELUDOM

PSECT SUMMARY

Name	Bytes	Attributes
\$CODE\$	2359	NOVEC,NOWRT, RD , EXE,NOSHR, LCL, REL, CON,NOPI,ALIGN(2)

Library Statistics

File	----- Total	Symbols Loaded	----- Percent	Pages Mapped	Processing Time
_\$255\$DUA28:[SYSLIB]LIB.L32;1	18619	52	0	1000	00:01.8

COMMAND QUALIFIERS

; BLISS/CHECK=(FIELD,INITIAL,OPTIMIZE)/LIS=LIS\$:ACLSUBR/OBJ=OBJ\$:ACLSUBR MSRC\$:ACLSUBR/UPDATE=(ENH\$:ACLSUBR)

; Size: 2359 code + 0 data bytes
; Run Time: 00:43.6
; Elapsed Time: 01:36.9
; Lines/CPU Min: 3192
; Lexemes/CPU-Min: 19767
; Memory Used: 278 pages
; Compilation Complete

0167 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

